

# Command tables for OpenOffice.org 2.0

The following tables list all available commands that are accessible through the GUI. The command names are used with the ".uno:" protocol scheme to define framework commands. These command URLs can be used to dispatch/execute, like ".uno:About" shows the about box. Please keep in mind that slot-URLs are deprecated for OpenOffice.org 2.0 and shouldn't be used anymore.

Abbreviations:

A = accelerator

M = menu

T = toolbox

S = status bar

- Global commands
- Writer commands
- Calc commands
- Draw/Impress commands
- Chart commands
- Math commands

## Global commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
AVMediaPlayer	AMT	SID_AVMEDIA_PLAYER	Media Player	6694
About	AMT	SID_ABOUT	About OpenOffice.org	5301
AbsoluteRecord	AMT	SID_FM_RECORD_ABSOLUTE	Absolute Record	10622
ActiveHelp	AMT	SID_HELPBALLOONS	Extended Tips	5403
AddDateField	AMT	SID_INSERT_DATEFIELD	Date Field	10936
AddDirect	AMT	SID_NEWDOCDIRECT	New	5537
AddField	AMT	SID_FM_ADD_FIELD	Add Field	10623
AddTable	AMT	SID_FM_ADDTABLE	Add Table	10722

AddWatch	AMT	SID_BASICIDE_ADDWATCH	Enable Watch	30769
AddressBookSource	AMT	SID_TEMPLATE_ADDRESSBOKSOURCE	Address Book Source	6655
AlignCenter	AMT	SID_OBJECT_ALIGN_CENTER	Centered	10132
AlignDown	AMT	SID_OBJECT_ALIGN_DOWN	Bottom	10136
AlignMiddle	AMT	SID_OBJECT_ALIGN_MIDDLE	Center	10135
AlignUp	AMT	SID_OBJECT_ALIGN_UP	Top	10134
Arc	AMT	SID_DRAW_ARC	Arc	10114
ArrowShapes	AMT	SID_DRAWTBX_CS_ARROW	Block Arrows	11049
AutoControlFocus	AMT	SID_FM_AUTOCONTROLFOCUS	Automatic Control Focus	10763
AutoCorrectDlg	AMT	SID_AUTO_CORRECT_DLG	AutoCorrect	10424
AutoFilter	AMT	SID_FM_AUTOFILTER	AutoFilter	10716
AutoFormat	AMT	SID_AUTOFORMAT	AutoFormat	10242
AutoPilotAddressDataSource	AMT	SID_ADDRESS_DATA_SOURCE	AutoPilot: Address Data Source	10934
AutoPilotMenu	AMT	SID_AUTOPILOTMENU	Wizards	6381
AutoPilotPresentations	AMT	SID_SD_AUTOPILOT	AutoPilot: Presentation	10425
AvailableToolbars	AMT	SID_AVAILABLE_TOOLBARS	Toolbars	6698
BackgroundColor	AMT	SID_BACKGROUND_COLOR	Background Color	10185
BackgroundPatternController	AMT	SID_BACKGROUND_PATTERN	Background Pattern	10186
BasicBreak	AMT	SID_BASICBREAK	Interrupt Macro	6521
BasicIDEAppear	AMT	SID_BASICIDE_APPEAR	Edit Macros	30783
BasicShapes	AMT	SID_DRAWTBX_CS_BASIC	Basic Shapes	11047
BasicStepInto	AMT	SID_BASICSTEPINTO	Step Into	5956
BasicStepOut	AMT	SID_BASICSTEPOUT	Step Out	5963
BasicStepOver	AMT	SID_BASICSTEPOVER	Step Over	5957
BasicStop	AMT	SID_BASICSTOP	Stop Macro	5958
BezierClose	AMT	SID_BEZIER_CLOSE	Close BÃ©zier	10122
BezierConvert	AMT	SID_BEZIER_CONVERT	Convert to Curve	27065
BezierCutLine	AMT	SID_BEZIER_CUTLINE	Split Curve	10127
BezierDelete	AMT	SID_BEZIER_DELETE	Delete Points	10120
BezierEdge	AMT	SID_BEZIER_EDGE	Corner Point	27066
BezierEliminatePoints	AMT	SID_BEZIER_ELIMINATE_POINTS	Eliminate Points	27030
BezierFill	AMT	SID_DRAW_BEZIER_FILL	Curve, Filled	10118

BezierInsert	AMT	SID_BEZIER_INSERT	Insert Points	10119
BezierMove	AMT	SID_BEZIER_MOVE	Move Points	10121
BezierSmooth	AMT	SID_BEZIER_SMOOTH	Smooth Transition	10123
BezierSymmetric	AMT	SID_BEZIER_SYMMTR	Symmetric Transition	27067
Bezier_Unfilled	AMT	SID_DRAW_BEZIER_NOFILL	Curve	10397
BibliographyComponent	AMT	SID_COMP_BIBLIOGRAPHY	Bibliography Database	10880
BmpMask	AMT	SID_BMPMASK	Eyedropper	10350
Bold	AMT	SID_ATTR_CHAR_WEIGHT	Bold	10009
BringToFront	AMT	SID_FRAME_TO_TOP	Bring to Front	10286
BrowseView	AMT	SID_BROWSER_MODE	Web Layout	6313
CalloutShapes	AMT	SID_DRAWTBX_CS_CALLOUT	Callouts	11051
CenterPara	AMT	SID_ATTR_PARA_ADJUST_CENTER	Centered	10030
ChangeCaseToFullWidth	AMT	SID_TRANSLITERATE_FULLWIDTH	Full-width	10915
ChangeCaseToHalfWidth	AMT	SID_TRANSLITERATE_HALFWIDTH	Half-width	10914
ChangeCaseToHiragana	AMT	SID_TRANSLITERATE_HIRAGANA	Hiragana	10916
ChangeCaseToKatakana	AMT	SID_TRANSLITERATE_KATAGANA	Katakana	10917
ChangeCaseToLower	AMT	SID_TRANSLITERATE_LOWER	Lowercase	10913
ChangeCaseToUpper	AMT	SID_TRANSLITERATE_UPPER	Uppercase	10912
CharFontName	AMT	SID_ATTR_CHAR_FONT	Font Name	10007
CheckBox	AMT	SID_FM_CHECKBOX	Check Box	10596
Checkbox	AMT	SID_INSERT_CHECKBOX	Check Box	10148
ChineseConversion	AMT	SID_CHINESE_CONVERSION	Chinese translation	11016
ChooseControls	AMT	SID_CHOOSE_CONTROLS	Insert Controls	10144
ChooseMacro	AMT	SID_BASICIDE_CHOOSEMACRO	Select Macro	30770
ChoosePolygon	AMT	SID_CHOOSE_POLYGON	Symbol Selection	10162
Circle	AMT	SID_DRAW_CIRCLE	Circle	10385
CircleArc	AMT	SID_DRAW_CIRCLEARC	Circle Arc	10390
CircleCut	AMT	SID_DRAW_CIRCLECUT	Circle Segment	10115
CircleCut_Unfilled	AMT	SID_DRAW_CIRCLECUT_NOFILL	Circle Segment, Unfilled	10391
CirclePie	AMT	SID_DRAW_CIRCLEPIE	Circle Pie	10388
CirclePie_Unfilled	AMT	SID_DRAW_CIRCLEPIE_NOFILL	Circle Pie, Unfilled	10389
Circle_Unfilled	AMT	SID_DRAW_CIRCLE_NOFILL	Circle, Unfilled	10386

ClearHistory	AMT	SID_CLEARHISTORY	Delete History	5703
ClearOutline	AMT	SID_OUTLINE_DELETEALL	Remove	10234
CloseDoc	AMT	SID_CLOSEDOC	Close	5503
CloseWin	AMT	SID_CLOSEWIN	Close Window	5621
Color	AMT	SID_ATTR_CHAR_COLOR	Font Color	10017
ColorControl	AMT	SID_COLOR_CONTROL	Color Bar	10417
ColorSettings	AMT	SID_COLOR_SETTINGS	Color	11044
ComboBox	AMT	SID_FM_COMBOBOX	Combo Box	10601
Combobox	AMT	SID_INSERT_COMBOBOX	Combo Box	10192
CommonAlignBottom	AMT	SID_ALIGN_ANY_BOTTOM	Bottom	11008
CommonAlignHorizontalCenter	AMT	SID_ALIGN_ANY_HCENTER	Centered	11003
CommonAlignHorizontalDefault	AMT	SID_ALIGN_ANY_HDEFAULT	Default	11009
CommonAlignJustified	AMT	SID_ALIGN_ANY_JUSTIFIED	Justified	11005
CommonAlignLeft	AMT	SID_ALIGN_ANY_LEFT	Left	11002
CommonAlignRight	AMT	SID_ALIGN_ANY_RIGHT	Right	11004
CommonAlignTop	AMT	SID_ALIGN_ANY_TOP	Top	11006
CommonAlignVerticalCenter	AMT	SID_ALIGN_ANY_VCENTER	Center	11007
CommonAlignVerticalDefault	AMT	SID_ALIGN_ANY_VDEFAULT	Default	11010
CompareDocuments	AMT	SID_DOCUMENT_COMPARE	Compare Document	6586
CompileBasic	AMT	SID_BASICCOMPILE	Compile	5954
Config	AMT	SID_FM_CONFIG	Controls	10593
ConfigureDialog	AMT	SID_CONFIG	Customize	5904
Context	S	SID_CONTEXT	Current Context	5310
ContourDialog	AMT	SID_CONTOUR_DLG	Edit Contour	10334
ControlProperties	AMT	SID_FM_CTL_PROPERTIES	Control	10613
ConvertToButton	AMT	SID_FM_CONVERTTO_BUTTON	Replace with Button	10735
ConvertToCheckBox	AMT	SID_FM_CONVERTTO_CHECKBOX	Replace with Check Box	10738
ConvertToCombo	AMT	SID_FM_CONVERTTO_COMBOBOX	Replace with Combo Box	10741
ConvertToCurrency	AMT	SID_FM_CONVERTTO_CURRENCY	Replace with Currency Field	10748
ConvertToDate	AMT	SID_FM_CONVERTTO_DATE	Replace with Date Field	10745
ConvertToEdit	AMT	SID_FM_CONVERTTO_EDIT	Replace with Text Box	10734
ConvertToFileControl	AMT	SID_FM_CONVERTTO_FILECONTROL	Replace with File Selection	10744

ConvertToFixed	AMT	SID_FM_CONVERTTO_FIXEDTEXT	Replace with Label Field	10736
ConvertToFormatted	AMT	SID_FM_CONVERTTO_FORMATTED	Replace with Formatted Field	10751
ConvertToGroup	AMT	SID_FM_CONVERTTO_GROUPBOX	Replace with Group Box	10740
ConvertToImageBtn	AMT	SID_FM_CONVERTTO_IMAGEBUTTON	Replace with Image Button	10743
ConvertToImageControl	AMT	SID_FM_CONVERTTO_IMAGECONTROL	Replace with Image Control	10750
ConvertToList	AMT	SID_FM_CONVERTTO_LISTBOX	Replace with List Box	10737
ConvertToNavigationBar	AMT	SID_FM_CONVERTTO_NAVIGATIONBAR	Replace with Navigation Bar	10772
ConvertToNumeric	AMT	SID_FM_CONVERTTO_NUMERIC	Replace with Numerical Field	10747
ConvertToPattern	AMT	SID_FM_CONVERTTO_PATTERN	Replace with Pattern Field	10749
ConvertToRadio	AMT	SID_FM_CONVERTTO_RADIOBUTTON	Replace with Radio Button	10739
ConvertToScrollBar	AMT	SID_FM_CONVERTTO_SCROLLBAR	Replace with Scrollbar	10770
ConvertToSpinButton	AMT	SID_FM_CONVERTTO_SPINBUTTON	Replace with Spin Button	10771
ConvertToTime	AMT	SID_FM_CONVERTTO_TIME	Replace with Time Field	10746
Copy	AMT	SID_COPY	Copy	5711
CountAll	AMT	SID_FM_COUNTALL	Records	10717
CurrencyField	AMT	SID_FM_CURRENCYFIELD	Currency Field	10707
CurrentDate	S	SID_CURRENTDATE	Current Date	5312
CurrentTime	S	SID_CURRENTTIME	Current Time	5311
Cut	AMT	SID_CUT	Cut	5710
DSBrowserExplorer	AMT	SID_DSBROWSER_EXPLORER	Explorer On/Off	10764
DateField	AMT	SID_FM_DATEFIELD	Date Field	10704
DecrementIndent	AMT	SID_DEC_INDENT	Decrease Indent	10461
DefaultBullet	AMT	FN_NUM_BULLET_ON	Bullets On/Off	20138
DefaultNumbering	AMT	FN_NUM_NUMBERING_ON	Numbering On/Off	20144
Delete	AMT	SID_DELETE	Delete Contents	5713
DeleteFrame	AMT	SID_DELETE_FRAME	Delete Frame	5652
DeleteRecord	AMT	SID_FM_RECORD_DELETE	Delete Record	10621
DesignerDialog	AMT	SID_STYLE_DESIGNER	Styles and Formatting	5539
DistributeSelection	AMT	SID_DISTRIBUTE_DLG	Distribution	5683
DrawCaption	AMT	SID_DRAW_CAPTION	Callouts	10254
DrawText	AMT	SID_DRAW_TEXT	Text	10253
Edit	AMT	SID_FM_EDIT	Text Box	10599

EditDoc	AMT	SID_EDITDOC	Edit File	6312
EditFrameSet	AMT	SID_EDIT_FRAMESET	Edit FrameSet	5646
Ellipse	AMT	SID_DRAW_ELLIPSE	Ellipse	10110
EllipseCut	AMT	SID_DRAW_ELLIPSECUT	Ellipse Segment	10392
EllipseCut_Unfilled	AMT	SID_DRAW_ELLIPSECUT_NOFILL	Ellipse Segment, unfilled	10393
Ellipse_Unfilled	AMT	SID_DRAW_ELLIPSE_NOFILL	Ellipse, Unfilled	10384
EnterGroup	AMT	SID_ENTER_GROUP	Enter Group	27096
ExportDirectToPDF	AMT	SID_DIRECTEXPORTDOCASPDF	Export Directly as PDF	6674
ExportTo	AMT	SID_EXPORTDOC	Export	5829
ExportToPDF	AMT	SID_EXPORTDOCASPDF	Export as PDF	6673
ExtendedHelp	AMT	SID_EXTENDEDHELP	What's This?	5402
Extrusion3DColor	AMT	SID_EXTRUSION_3D_COLOR	3D Color	10969
ExtrusionDepth	AMT	SID_EXTRUSION_DEPTH	Extrusion	10970
ExtrusionDepthDialog	AMT	SID_EXTRUSION_DEPTH_DIALOG	Extrusion Depth	10976
ExtrusionDepthFloater	AMT	SID_EXTRUSION_DEPTH_FLOATER	Depth	10965
ExtrusionDirectionFloater	AMT	SID_EXTRUSION_DIRECTION_FLOATER	Direction	10966
ExtrusionLightingFloater	AMT	SID_EXTRUSION_LIGHTING_FLOATER	Lighting	10967
ExtrusionSurfaceFloater	AMT	SID_EXTRUSION_SURFACE_FLOATER	Surface	10968
ExtrusionTiltDown	AMT	SID_EXTRUSION_TILT_DOWN	Tilt Down	10961
ExtrusionTiltLeft	AMT	SID_EXTRUSION_TILT_LEFT	Tilt Left	10963
ExtrusionTiltRight	AMT	SID_EXTRUSION_TILT_RIGHT	Tilt Right	10964
ExtrusionTiltUp	AMT	SID_EXTRUSION_TILT_UP	Tilt Up	10962
ExtrusionToggle	AMT	SID_EXTRUSION_TOOGLE	Extrusion On/Off	10960
FileControl	AMT	SID_FM_FILECONTROL	File Selection	10605
FileDocument	AMT	SID_SAVEDOCTOBOOKMARK	File Document	6315
FillColor	AMT	SID_ATTR_FILL_COLOR	Fill Color	10165
FillShadow	AMT	SID_ATTR_FILL_SHADOW	Shadow	10299
FillStyle	AMT	SID_ATTR_FILL_STYLE	Area Style / Filling	10164
FilterCrit	AMT	SID_FM_FILTERCRIT	Standard Filter	10715
FirstRecord	AMT	SID_FM_RECORD_FIRST	First Record	10616
Flash	AMT	SID_ATTR_FLASH	Flash	10406
FlowChartShapes	AMT	SID_DRAWTBX_CS_FLOWCHART	Flowcharts	11050

FontDialog	AMT	SID_CHAR_DLG	Character	10296
FontHeight	AMT	SID_ATTR_CHAR_FONTHEIGHT	Font Size	10015
FontWork	AMT	SID_FONTWORK	Fontwork	10256
FontworkAlignmentFloater	AMT	SID_FONTWORK_ALIGNMENT_FLOATER	Fontwork Alignment	10981
FontworkCharacterSpacingFloater	AMT	SID_FONTWORK_CHARACTER_SPACING_FLOATER	Fontwork Character Spacing	10982
FontworkGalleryFloater	AMT	SID_FONTWORK_GALLERY_FLOATER	Fontwork Gallery	10977
FontworkSameLetterHeights	AMT	SID_FONTWORK_SAME_LETTER_HEIGHTS	Fontwork Same Letter Heights	10980
FontworkShapeTypes	AMT	SID_FONTWORK_SHAPE_TYPES	Fontwork Shape	10978
FormDesignTools	AMT	SID_FM_FORM_DESIGN_TOOLS	Form Design	11046
FormFilter	AMT	SID_FM_FILTER_START	Form-Based Filters	10729
FormFilterExecute	AMT	SID_FM_FILTER_EXECUTE	Apply Form-Based Filter	10731
FormFilterExit	AMT	SID_FM_FILTER_EXIT	Close	10730
FormFilterNavigator	AMT	SID_FM_FILTER_NAVIGATOR	Filter Navigation	10732
FormFiltered	AMT	SID_FM_FORM_FILTERED	Apply Filter	10723
FormProperties	AMT	SID_FM_PROPERTIES	Form	10614
FormatArea	AMT	SID_ATTRIBUTES_AREA	Area	10142
FormatGroup	AMT	SID_GROUP	Group	10454
FormatLine	AMT	SID_ATTRIBUTES_LINE	Line	10143
FormatMenu	AMT	SID_FORMATMENU	Format	5780
FormatPaintbrush	AMT	SID_FORMATPAINTBRUSH	Format Paintbrush	5715
FormatUngroup	AMT	SID_UNGROUP	Ungroup	10455
FormattedField	AMT	SID_FM_FORMATTEDFIELD	Formatted Field	10728
FrameContent	AMT	SID_FRAME_CONTENT	Contents	5826
FrameLineColor	AMT	SID_FRAME_LINECOLOR	Line Color (of the border)	10201
FrameName	AMT	SID_FRAME_NAME	Name	5825
FrameSpacing	AMT	SID_FRAMESPACING	FrameSet Spacing	6507
Freeline	AMT	SID_DRAW_FREELINE	Freeform Line, Filled	10463
Freeline_Unfilled	AMT	SID_DRAW_FREELINE_NOFILL	Freeform Line	10464
FullScreen	AMT	SID_WIN_FULLSCREEN	Full Screen	5627
Gallery	AMT	SID_GALLERY	Gallery	5960
GetColorTable	AMT	SID_GET_COLORTABLE	Color Palette	10441
GoDown	AMT	SID_CURSORDOWN	Move Down	5731

GoDownBlock	AMT	SID_CURSORPAGEDOWN	Page Down	5735
GoDownBlockSel	AMT	SID_CURSORPAGEDOWN_SEL	Select Page Down	26525
GoDownSel	AMT	SID_CURSORDOWN_SEL	Select Down	26521
GoLeft	AMT	SID_CURSORLEFT	Move Left	5733
GoLeftBlock	AMT	SID_CURSORPAGELEFT	Page Left	5738
GoLeftBlockSel	AMT	SID_CURSORPAGELEFT_SEL	Select Page Left	26528
GoLeftSel	AMT	SID_CURSORLEFT_SEL	Select Left	26523
GoRight	AMT	SID_CURSORRIGHT	Move Right	5734
GoRightSel	AMT	SID_CURSORRIGHT_SEL	Select Right	26524
GoToEndOfData	AMT	SID_CURSORENDOFFILE	To File End	5741
GoToEndOfDataSel	AMT	SID_CURSORENDOFFILE_SEL	Select to File End	26532
GoToEndOfRow	AMT	SID_CURSOREND	To Document End	5746
GoToEndOfRowSel	AMT	SID_CURSOREND_SEL	Select to Document End	26534
GoToStart	AMT	SID_CURSORTOPOFFILE	To File Begin	5742
GoToStartOfRow	AMT	SID_CURSORHOME	To Document Begin	5745
GoToStartOfRowSel	AMT	SID_CURSORHOME_SEL	Select to Document Begin	26533
GoToStartSel	AMT	SID_CURSORTOPOFFILE_SEL	Select to File Begin	26531
GoUp	AMT	SID_CURSORUP	Move Up	5732
GoUpBlock	AMT	SID_CURSORPAGEUP	Page Up	5736
GoUpBlockSel	AMT	SID_CURSORPAGEUP_SEL	Select Page Up	26526
GoUpSel	AMT	SID_CURSORUP_SEL	Select Up	26522
GrabControlFocus	AMT	SID_FM_GRABCONTROLFOCUS	Control Focus	10767
GrafAttrCrop	AMT	SID_ATTR_GRAF_CROP	Crop	10883
GrafBlue	AMT	SID_ATTR_GRAF_BLUE	Blue	10867
GrafContrast	AMT	SID_ATTR_GRAF_CONTRAST	Contrast	10864
GrafGamma	AMT	SID_ATTR_GRAF_GAMMA	Gamma	10868
GrafGreen	AMT	SID_ATTR_GRAF_GREEN	Green	10866
GrafInvert	AMT	SID_ATTR_GRAF_INVERT	Invert	10870
GrafLuminance	AMT	SID_ATTR_GRAF_LUMINANCE	Brightness	10863
GrafMode	AMT	SID_ATTR_GRAF_MODE	Graphics mode	10871
GrafRed	AMT	SID_ATTR_GRAF_RED	Red	10865
GrafTransparence	AMT	SID_ATTR_GRAF_TRANSPARENCE	Transparency	10869



GraphicFilterInvert	AMT	SID_GRFFILTER_INVERT	Invert	10470
GraphicFilterMosaic	AMT	SID_GRFFILTER_MOSAIC	Mosaic	10475
GraphicFilterPopart	AMT	SID_GRFFILTER_POPART	Pop Art	10478
GraphicFilterPoster	AMT	SID_GRFFILTER_POSTER	Posterize	10477
GraphicFilterRelief	AMT	SID_GRFFILTER_EMBOSS	Relief	10476
GraphicFilterRemoveNoise	AMT	SID_GRFFILTER_REMOVENOISE	Remove Noise	10473
GraphicFilterSepia	AMT	SID_GRFFILTER_SEPIA	Aging	10479
GraphicFilterSharpen	AMT	SID_GRFFILTER_SHARPEN	Sharpen	10472
GraphicFilterSmooth	AMT	SID_GRFFILTER_SMOOTH	Smooth	10471
GraphicFilterSobel	AMT	SID_GRFFILTER_SOBEL	Charcoal Sketch	10474
GraphicFilterSolarize	AMT	SID_GRFFILTER_SOLARIZE	Solarization	10480
GraphicFilterToolbox	AMT	SID_GRFFILTER	Filter	10469
Grid	AMT	SID_FM_DBGRID	Table Control	10603
GridUse	AMT	SID_GRID_USE	Snap to Grid	27154
GridVisible	AMT	SID_GRID_VISIBLE	Display Grid	27322
Group	AMT	SID_OUTLINE_MAKE	Group	26331
GroupBox	AMT	SID_FM_GROUPBOX	Group Box	10598
Groupbox	AMT	SID_INSERT_GROUPBOX	Group Box	10189
HFixedLine	AMT	SID_INSERT_HFIXEDLINE	Horizontal Line	10928
HScrollbar	AMT	SID_INSERT_HSCROLLBAR	Horizontal Scroll Bar	10194
HangulHanjaConversion	AMT	SID_HANGUL_HANJA_CONVERSION	Hangul/Hanja Conversion	10959
HelpChooseFile	AMT	SID_HELP_HELPFILEBOX	Choose Help File	5419
HelpIndex	AMT	SID_HELPINDEX	OpenOffice.org Help	5401
HelpMenu	AMT	SID_HELPMENU	Help	5410
HelpOnHelp	AMT	SID_HELPONHELP	Help on Help	5400
HelpSupport	AMT	SID_HELP_SUPPORTPAGE	Support	6683
HelperDialog	AMT	SID_HELP_PI	Help Agent	5962
HelplinesMove	AMT	SID_HELPLINES_MOVE	Guides When Moving	27153
HideDetail	AMT	SID_OUTLINE_HIDE	Hide Details	26329
HideSpellMark	AMT	SID_AUTOSPELL_MARKOFF	Do Not Mark Errors	12022
HyperlinkDialog	AMT	SID_HYPERLINK_DIALOG	Hyperlink	5678
ImageControl	AMT	SID_FM_IMAGECONTROL	Image Control	10710

ImageMapDialog	AMT	SID_IMAP	ImageMap	10371
Imagebutton	AMT	SID_FM_IMAGEBUTTON	Image Button	10604
IncrementIndent	AMT	SID_INC_INDENT	Increase Indent	10462
InsertAVMedia	AMT	SID_INSERT_AVMEDIA	Movie and Sound	6696
InsertAnnotation	AMT	SID_INSERT_POSTIT	Note	26276
InsertApplet	AMT	SID_INSERT_APPLET	Applet	5673
InsertBusinessCard	AMT	FN_BUSINESS_CARD	Insert business cards	21052
InsertCurrencyField	AMT	SID_INSERT_CURRENCYFIELD	Currency Field	10939
InsertDoc	AMT	SID_INSERTDOC	File	5532
InsertDraw	AMT	SID_INSERT_DRAW	Show Draw Functions	10244
InsertEdit	AMT	SID_INSERT_EDIT	Text Box	10190
InsertFileControl	AMT	SID_INSERT_FILECONTROL	File Selection	10942
InsertFixedText	AMT	SID_INSERT_FIXEDTEXT	Label field	10188
InsertFormattedField	AMT	SID_INSERT_FORMATTEDFIELD	Formatted Field	10940
InsertGraphic	AMT	SID_INSERT_GRAPHIC	From File	10241
InsertHyperlink	AMT	SID_HYPERLINK_INSERT	Hyperlink Bar	10360
InsertImage	AMT	SID_INSERT_IMAGE	Insert from Image Editor	27105
InsertImageControl	AMT	SID_INSERT_IMAGECONTROL	Image Control	10926
InsertLabels	AMT	FN_LABEL	Insert Labels	21051
InsertListbox	AMT	SID_INSERT_LISTBOX	List Box	10191
InsertMath	AMT	SID_INSERT_MATH	Formula	27106
InsertMode	AMT	SID_ATTR_INSERT	Insert Mode	10221
InsertNumericField	AMT	SID_INSERT_NUMERICFIELD	Numeric Field	10938
InsertObject	AMT	SID_INSERT_OBJECT	OLE Object	5561
InsertObjectChart	AMT	SID_INSERT_DIAGRAM	Chart	10140
InsertObjectFloatingFrame	AMT	SID_INSERT_FLOATINGFRAME	Floating Frame	5563
InsertPatternField	AMT	SID_INSERT_PATTERNFIELD	Pattern Field	10941
InsertPlugin	AMT	SID_INSERT_PLUGIN	Plug-in	5672
InsertPushbutton	AMT	SID_INSERT_PUSHBUTTON	Button	10146
InsertSound	AMT	SID_INSERT_SOUND	Sound	5676
InsertSpreadsheet	AMT	SID_ATTR_TABLE	Spreadsheet	10217
InsertSymbol	AMT	SID_CHARMAP	Special Character	10503

InsertTextFrame	AMT	SID_INSERT_FRAME	Insert Text Frame	10240
InsertTimeField	AMT	SID_INSERT_TIMEFIELD	Time Field	10937
InsertVideo	AMT	SID_INSERT_VIDEO	Video	5677
InternetDialog	AMT	SID_INET_DLG	Internet Options	10416
Intersect	AMT	SID_POLY_INTERSECT	Intersect	5681
IsLoading	AMT	SID_DOC_LOADING	Load Document	5585
Italic	AMT	SID_ATTR_CHAR_POSTURE	Italic	10008
JustifyPara	AMT	SID_ATTR_PARA_ADJUST_BLOCK	Justified	10031
Label	AMT	SID_FM_FIXEDTEXT	Label Field	10597
LastRecord	AMT	SID_FM_RECORD_LAST	Last Record	10619
LaunchStarImage	AMT	SID_SIM_START	Start Image Editor	30000
LeaveGroup	AMT	SID_LEAVE_GROUP	Exit group	27097
LeftPara	AMT	SID_ATTR_PARA_ADJUST_LEFT	Align Left	10028
LibSelector	AMT	SID_BASICIDE_LIBSELECTOR	Current Library	30787
Line	AMT	SID_DRAW_LINE	Line	10102
LineDash	AMT	SID_ATTR_LINE_DASH	Line Dash/Dot	10170
LineEndStyle	AMT	SID_ATTR_LINEEND_STYLE	Arrow Style	10301
LineStyle	AMT	SID_FRAME_LINestyle	Line Style	10200
LineWidth	AMT	SID_ATTR_LINE_WIDTH	Line Width	10171
Line_Diagonal	AMT	SID_DRAW_XLINE	Line (45°)	10103
ListBox	AMT	SID_FM_LISTBOX	List Box	10600
LoadBasic	AMT	SID_BASICLOAD	Insert BASIC Source	5951
LoadConfiguration	AMT	SID_LOADCONFIG	Load Configuration	5933
MacroDialog	AMT	SID_BASICCHOOSEr	OpenOffice.org Basic	5959
MacroOrganizer	AMT	SID_MACROORGANIZER	NO DESCRIPTION AVAILABLE	6691
MacroRecorder	AMT	SID_RECORDMACRO	Record Macro	6669
MacroSignature	AMT	SID_MACRO_SIGNATURE	Digital Signature	6704
ManageBreakPoints	AMT	SID_BASICIDE_MANAGEBRKPNTS	Manage Breakpoints	30810
MatchGroup	AMT	SID_BASICIDE_MATCHGROUP	Find Parenthesis	30782
MenuBarVisible	AMT	SID_TOGGLE_MENUBAR	Menu On/Off	6661
Merge	AMT	SID_POLY_MERGE	Merge	5679
MergeDocuments	AMT	SID_DOCUMENT_MERGE	Merge Document	6587

ModifiedStatus	S	SID_DOC_MODIFIED	Document Modified	5584
ModifyFrame	AMT	SID_MODIFY_FRAME	Frame Properties	5651
ModuleDialog	AMT	SID_BASICIDE_MODULEDLG	Select Module	30773
MoreControls	AMT	SID_FM_MORE_CONTROLS	More Controls	11045
NavigationBar	AMT	SID_FM_NAVIGATIONBAR	Navigation Bar	10607
Navigator	AMT	SID_NAVIGATOR	Navigator	10366
NewDoc	AMT	SID_NEWDOC	New Document From Template	5500
NewFrameSet	AMT	SID_NEWFRAMESET	New FrameSet	6400
NewPresentation	AMT	SID_NEWSD	New Presentation	6686
NewRecord	AMT	SID_FM_RECORD_NEW	New Record	10620
NewWindow	AMT	SID_NEWWINDOW	New Window	5620
NextRecord	AMT	SID_FM_RECORD_NEXT	Next Record	10617
NumericField	AMT	SID_FM_NUMERICFIELD	Numerical Field	10706
ObjectAlign	AMT	SID_OBJECT_ALIGN	Alignment	10130
ObjectAlignLeft	AMT	SID_OBJECT_ALIGN_LEFT	Left	10131
ObjectAlignRight	AMT	SID_OBJECT_ALIGN_RIGHT	Right	10133
ObjectBackOne	AMT	SID_FRAME_DOWN	Back One	26408
ObjectCatalog	AMT	SID_BASICIDE_OBJCAT	Object Catalog	30774
ObjectForwardOne	AMT	SID_FRAME_UP	Forward One	26407
ObjectMenue	AMT	SID_OBJECT	Object	5575
OnlineRegistrationDlg	AMT	SID_ONLINE_REGISTRATION	Registration	6537
Open	AMT	SID_OPENDOC	Open	5501
OpenHyperlinkOnCursor	AMT	SID_OPEN_HYPERLINK	Open Hyperlink	10955
OpenReadOnly	AMT	SID_FM_OPEN_READONLY	Open in Design Mode	10709
OpenTemplate	AMT	SID_OPENTEMPLATE	Edit	5594
OpenUrl	AMT	SID_OPENURL	Load URL	5596
OpenXMLFilterSettings	AMT	SID_OPEN_XML_FILTERSETTINGS	XML Filter Settings	10958
OptionsTreeDialog	AMT	SID_OPTIONS_TREEDIALOG	Options	31630
OrderCrit	AMT	SID_FM_ORDERCRIT	Sort	10714
Organizer	AMT	SID_ORGANIZER	Organize	5540
OutlineBullet	AMT	SID_OUTLINE_BULLET	Bullets and Numbering	10156
OutlineCollapse	AMT	SID_OUTLINE_COLLAPSE	Hide Subpoints	10231

OutlineCollapseAll	AMT	SID_OUTLINE_COLLAPSE_ALL	First Level	10155
OutlineDown	AMT	SID_OUTLINE_DOWN	Move Down	10151
OutlineExpand	AMT	SID_OUTLINE_EXPAND	Show Subpoints	10233
OutlineExpandAll	AMT	SID_OUTLINE_EXPAND_ALL	All Levels	10232
OutlineFont	AMT	SID_ATTR_CHAR_CONTOUR	Outline	10012
OutlineFormat	AMT	SID_OUTLINE_FORMAT	Formatting On/Off	10154
OutlineLeft	AMT	SID_OUTLINE_LEFT	Promote	10152
OutlineRight	AMT	SID_OUTLINE_RIGHT	Demote	10153
OutlineUp	AMT	SID_OUTLINE_UP	Move Up	10150
ParaLeftToRight	AMT	SID_ATTR_PARA_LEFT_TO_RIGHT	Left-To-Right	10950
ParaRightToLeft	AMT	SID_ATTR_PARA_RIGHT_TO_LEFT	Right-To-Left	10951
ParagraphDialog	AMT	SID_PARA_DLG	Paragraph	10297
Paste	AMT	SID_PASTE	Paste	5712
PatternField	AMT	SID_FM_PATTERNFIELD	Pattern Field	10708
PickList	AMT	SID_PICKLIST	File	5510
Pie	AMT	SID_DRAW_PIE	Ellipse Pie	10112
Pie_Unfilled	AMT	SID_DRAW_PIE_NOFILL	Ellipse Pie, Unfilled	10387
PlugInsActive	AMT	SID_PLUGINS_ACTIVE	Plug-in	6314
PolyFormen	AMT	SID_POLY_FORMEN	Shapes	5682
Polygon_Diagonal	AMT	SID_DRAW_XPOLYGON	Polygon (45°), Filled	10394
Polygon_Diagonal_Unfilled	AMT	SID_DRAW_XPOLYGON_NOFILL	Polygon (45°)	10396
Polygon_Unfilled	AMT	SID_DRAW_POLYGON_NOFILL	Polygon	10395
PrevRecord	AMT	SID_FM_RECORD_PREV	Previous Record	10618
Preview	AMT	SID_INSERT_PREVIEW	Preview	10196
Print	AMT	SID_PRINTDOC	Print	5504
PrintDefault	AMT	SID_PRINTDOCDIRECT	Print File Directly	5509
PrintPreview	AMT	SID_PRINTPREVIEW	Page Preview	5325
PrinterSetup	AMT	SID_SETUPPRINTER	Printer Settings	5302
ProgressBar	AMT	SID_INSERT_PROGRESSBAR	Progress Bar	10927
Pushbutton	AMT	SID_FM_PUSHBUTTON	Push Button	10594
Quit	AMT	SID_QUITAPP	Exit	5300
RadioButton	AMT	SID_FM_RADIOBUTTON	Option Button	10595

Radiobutton	AMT	SID_INSERT_RADIOBUTTON	Option Button	10147
RecFromText	AMT	SID_FM_RECORD_FROM_TEXT	Text -> Record	10625
RecSave	AMT	SID_FM_RECORD_SAVE	Save Record	10627
RecSearch	AMT	SID_FM_SEARCH	Find Record	10725
RecText	AMT	SID_FM_RECORD_TEXT	Record	10624
RecTotal	AMT	SID_FM_RECORD_TOTAL	Total No. of Records	10626
RecUndo	AMT	SID_FM_RECORD_UNDO	Undo: Data entry	10630
RecentFileList	AMT	SID_RECENTFILELIST	Recent Documents	6697
Rect	AMT	SID_DRAW_RECT	Rectangle	10104
Rect_Rounded	AMT	SID_DRAW_RECT_ROUND	Rectangle, Rounded	10105
Rect_Rounded_Unfilled	AMT	SID_DRAW_RECT_ROUND_NOFILL	Rounded Rectangle, Unfilled	10379
Rect_Unfilled	AMT	SID_DRAW_RECT_NOFILL	Rectangle, Unfilled	10378
Redo	AMT	SID_REDO	Can't Restore	5700
Refresh	AMT	SID_FM_REFRESH	Refresh	10724
Reload	AMT	SID_RELOAD	Reload	5508
RemoveFilter	AMT	SID_FM_FILTER_REMOVE	Remove Filter	10762
RemoveFilterSort	AMT	SID_FM_REMOVE_FILTER_SORT	Remove Filter/Sort	10711
Repaint	AMT	SID_REPAINT	Redraw	26012
RepeatAction	AMT	SID_REPEAT	NO DESCRIPTION AVAILABLE	5702
RightPara	AMT	SID_ATTR_PARA_ADJUST_RIGHT	Align Right	10029
RubyDialog	AMT	SID_RUBY_DIALOG	Asian phonetic guide	6656
RunBasic	AMT	SID_BASICRUN	Run BASIC	5955
RunMacro	AMT	SID_RUNMACRO	Run Macro	6692
Save	AMT	SID_SAVEDOC	Save	5505
SaveAll	AMT	SID_SAVEDOCS	Save All	5309
SaveAs	AMT	SID_SAVEASDOC	Save As	5502
SaveAsTemplate	AMT	SID_DOCTEMPLATE	Save	5538
SaveBasicAs	AMT	SID_BASICSAVEAS	Save BASIC	5953
SaveConfiguration	AMT	SID_SAVECONFIG	Save configuration	5930
SbaExecuteSql	AMT	SID_FM_EXECUTE	Run Query	10721
SbaNativeSql	AMT	SID_FM_NATIVESQL	Run SQL command directly	10720
ScEditOptions	AMT	SID_SC_EDITOPTIONS	Spreadsheet Options	10435

Scan	AMT	SID_SCAN	Scan	10330
SchEditOptions	AMT	SID_SCH_EDITOPTIONS	Chart Options	10437
ScriptOrganizer	AMT	SID_SCRIPTORGANIZER	Organize Macros	6690
ScrollBar	AMT	SID_FM_SCROLLBAR	Scrollbar	10768
SdEditOptions	AMT	SID_SD_EDITOPTIONS	Presentation Options	10434
SdGraphicOptions	AMT	SID_SD_GRAPHIC_OPTIONS	Presentation Graphic Options	10447
SearchDialog	AMT	SID_SEARCH_DLG	Find & Replace	5961
Select	AMT	SID_SELECT	Select All	5720
SelectAll	AMT	SID_SELECTALL	Select All	5723
SelectMode	AMT	SID_INSERT_SELECT	Select	10198
SelectObject	AMT	SID_OBJECT_SELECT	Select	10128
SendFax	AMT	FN_FAX	Send Default Fax	20028
SendMail	AMT	SID_MAIL_SENDDOC	Document as E-mail	5331
SendMailDocAsPDF	AMT	SID_MAIL_SENDDOCASPDF	Document as PDF Attachment	6672
SendToBack	AMT	SID_FRAME_TO_BOTTOM	Send to Back	10287
SetBorderStyle	AMT	SID_ATTR_BORDER	Borders	10187
SetDefault	AMT	SID_SET_DEFAULT	Default Formatting	10456
SetDocumentProperties	AMT	SID_DOCINFO	Properties	5535
SetObjectToBackground	AMT	SID_OBJECT_HELL	To Background	10282
SetObjectToForeground	AMT	SID_OBJECT_HEAVEN	To Foreground	10283
Shadowed	AMT	SID_ATTR_CHAR_SHADOWED	Shadow	10010
ShowBrowser	AMT	SID_SHOW_BROWSER	Display Properties	10163
ShowDataNavigator	AMT	SID_FM_SHOW_DATANAVIGATOR	Data Navigator	10773
ShowDetail	AMT	SID_OUTLINE_SHOW	Show Details	26330
ShowFmExplorer	AMT	SID_FM_SHOW_FMEEXPLORER	Form Navigator	10633
ShowImeStatusWindow	AMT	SID_SHOW_IME_STATUS_WINDOW	Input Method Status	6680
ShowItemBrowser	AMT	SID_SHOW_ITEMBROWSER	Item Browser On/Off	11001
ShowPropBrowser	AMT	SID_SHOW_PROPERTYBROWSER	Properties	10943
Signature	AMT	SID_SIGNATURE	Digital Signatures	6643
SimEditOptions	AMT	SID_SIM_EDITOPTIONS	Image Options	10438
Size	S	SID_ATTR_SIZE	Size	10224
SmEditOptions	AMT	SID_SM_EDITOPTIONS	Formula Options	10436

SortDown	AMT	SID_FM_SORTDOWN	Sort Descending	10713
Sortup	AMT	SID_FM_SORTUP	Sort Ascending	10712
SourceView	AMT	SID_SOURCEVIEW	HTML Source	5675
SpacePara1	AMT	SID_ATTR_PARA_LINESPACE_10	Line Spacing: 1	10034
SpacePara15	AMT	SID_ATTR_PARA_LINESPACE_15	Line Spacing : 1.5	10035
SpacePara2	AMT	SID_ATTR_PARA_LINESPACE_20	Line Spacing : 2	10036
SpellDialog	AMT	SID_SPELL_DIALOG	Spellcheck	10243
SpellOnline	AMT	SID_AUTOSPELL_CHECK	AutoSpellcheck	12021
SpinButton	AMT	SID_FM_SPINBUTTON	Spin Button	10769
Spinbutton	AMT	SID_INSERT_SPINBUTTON	Spin Button	10193
SplitHorizontal	AMT	SID_SPLIT_HORIZONTAL	Split Frame Horizontally	5647
SplitParentHorizontal	AMT	SID_SPLIT_PARENT_HORIZONTAL	Split FrameSet Horizontally	5649
SplitParentVertical	AMT	SID_SPLIT_PARENT_VERTICAL	Split FrameSet Vertically	5650
SplitVertical	AMT	SID_SPLIT_VERTICAL	Split Frame Vertically	5648
Square	AMT	SID_DRAW_SQUARE	Square	10380
Square_Rounded	AMT	SID_DRAW_SQUARE_ROUND	Rounded Square	10381
Square_Rounded_Unfilled	AMT	SID_DRAW_SQUARE_ROUND_NOFILL	Rounded Square, Unfilled	10383
Square_Unfilled	AMT	SID_DRAW_SQUARE_NOFILL	Square, Unfilled	10382
StarShapes	AMT	SID_DRAWTBX_CS_STAR	Stars	11052
StateTableCell	S	SID_TABLE_CELL	Cell	10225
StatusBarVisible	AMT	SID_TOGGLESTATUSBAR	Status Bar	5920
StatusGetPosition	S	SID_BASICIDE_STAT_POS	Position	30806
StatusGetTitle	S	SID_BASICIDE_STAT_TITLE	Current Basic Module	30808
Stop	AMT	SID_BROWSE_STOP	Stop Loading	6302
StopRecording	AMT	SID_STOP_RECORDING	Stop Recording	6671
Strikeout	AMT	SID_ATTR_CHAR_STRIKEOUT	Strikethrough	10013
StyleApplyState	AMT	SID_STYLE_APPLY	NO DESCRIPTION AVAILABLE	5552
StyleCatalog	AMT	SID_STYLE_CATALOG	Catalog	5573
StyleNewByExample	AMT	SID_STYLE_NEW_BY_EXAMPLE	New Style from Selection	5555
StyleUpdateByExample	AMT	SID_STYLE_UPDATE_BY_EXAMPLE	Update Style	5556
SubScript	AMT	SID_SET_SUB_SCRIPT	Subscript	10295
Substract	AMT	SID_POLY_SUBSTRACT	Subtract	5680



SuperScript	AMT	SID_SET_SUPER_SCRIPT	Superscript	10294
SwEditOptions	AMT	SID_SW_EDITOPTIONS	Text Document Options	10433
SwitchControlDesignMode	AMT	SID_FM_DESIGN_MODE	Design Mode On/Off	10629
SymbolShapes	AMT	SID_DRAWTBX_CS_SYMBOL	Symbol Shapes	11048
TabDialog	AMT	SID_FM_TAB_DIALOG	Activation Order	10615
TaskBarVisible	AMT	SID_TASKBAR	NO DESCRIPTION AVAILABLE	5931
TestMode	AMT	SID_DIALOG_TESTMODE	Test Mode On/Off	10199
Text	AMT	SID_ATTR_CHAR	Text	10006
TextFitToSize	AMT	SID_ATTR_TEXT_FITTO_SIZE	Fit to Frame	10367
Text_Marquee	AMT	SID_DRAW_TEXT_MARQUEE	Text Animation	10465
TextdirectionLeftToRight	AMT	SID_TEXTDIRECTION_LEFT_TO_RIGHT	Text direction from left to right	10907
TextdirectionTopToBottom	AMT	SID_TEXTDIRECTION_TOP_TO_BOTTOM	Text direction from top to bottom	10908
Thesaurus	AMT	SID_THESAURUS	Thesaurus	10245
TimeField	AMT	SID_FM_TIMEFIELD	Time Field	10705
ToggleBreakPoint	AMT	SID_BASICIDE_TOGGLEBRKPNT	Breakpoint On/Off	30768
ToggleBreakPointEnabled	AMT	SID_BASICIDE_TOGGLEBRKPNTENABLED	Breakpoint Enabled/Disabled	30811
ToggleObjectBezierMode	AMT	SID_BEZIER_EDIT	Points	10126
ToggleObjectRotateMode	AMT	SID_OBJECT_ROTATE	Rotate	10129
ToolsMacroEdit	AMT	SID_EDITMACRO	Edit Macros	5802
TransformDialog	AMT	SID_ATTR_TRANSFORM	Position and Size	10087
TwainSelect	AMT	SID_TWAIN_SELECT	Select Source	10331
TwainTransfer	AMT	SID_TWAIN_TRANSFER	Request	10332
URLButton	AMT	SID_INSERT_URLBUTTON	URL Button	10197
Underline	AMT	SID_ATTR_CHAR_UNDERLINE	Underline	10014
Undo	AMT	SID_UNDO	Can't Undo	5701
Ungroup	AMT	SID_OUTLINE_REMOVE	Ungroup	26332
UseWizards	AMT	SID_FM_USE_WIZARDS	Wizards On/Off	10727
VFixedLine	AMT	SID_INSERT_VFIXEDLINE	Vertical Line	10929
VScrollbar	AMT	SID_INSERT_VSCROLLBAR	Vertical Scroll Bar	10195
VersionDialog	AMT	SID_VERSION	Versions	6583
VersionVisible	AMT	SID_VERSION_VISIBLE	Version Visible	5313
VerticalCaption	AMT	SID_DRAW_CAPTION_VERTICAL	Vertical Callouts	10906

VerticalText	AMT	SID_DRAW_TEXT_VERTICAL	Vertical Text	10905
ViewDataSourceBrowser	AMT	SID_VIEW_DATA_SOURCE_BROWSER	Data Sources	6660
ViewFormAsGrid	AMT	SID_FM_VIEW_AS_GRID	Data source as Table	10761
Window3D	AMT	SID_3D_WIN	3D Effects	10644
XLineColor	AMT	SID_ATTR_LINE_COLOR	Line Color	10172
XLineStyle	AMT	SID_ATTR_LINE_STYLE	Line Style	10169
Zoom	AMT	SID_ATTR_ZOOM	Zoom	10000
Zoom100Percent	AMT	SID_SIZE_REAL	Zoom 100%	10099
ZoomMinus	AMT	SID_ZOOM_IN	Zoom Out	10098
ZoomNext	AMT	SID_ZOOM_NEXT	Zoom Next	10402
ZoomObjects	AMT	SID_SIZE_OPTIMAL	Object Zoom	27099
ZoomOptimal	AMT	SID_SIZE_ALL	Optimal	10101
ZoomPage	AMT	SID_SIZE_PAGE	Zoom Page	10100
ZoomPageWidth	AMT	SID_SIZE_PAGE_WIDTH	Zoom Page Width	27098
ZoomPlus	AMT	SID_ZOOM_OUT	Zoom In	10097
ZoomPrevious	AMT	SID_ZOOM_PREV	Zoom Previous	10403
ZoomToolBox	AMT	SID_ZOOM_TOOLBOX	Zoom	10096

## Writer commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
AcceptTrackedChanges	AMT	FN_REDLINE_ACCEPT	Accept or Reject	21829
AddAllUnknownWords	AMT	FN_ADD_UNKNOWN	Add Unknown Words	20606
AlignBottom	AMT	FN_FRAME_ALIGN_VERT_BOTTOM	NO DESCRIPTION AVAILABLE	20479
AlignCharBottom	AMT	FN_FRAME_ALIGN_VERT_CHAR_BOTTOM	Align to Bottom of Character	20569
AlignCharTop	AMT	FN_FRAME_ALIGN_VERT_CHAR_TOP	Align to Top of Character	20568
AlignHorizontalCenter	AMT	FN_FRAME_ALIGN_HORZ_CENTER	NO DESCRIPTION AVAILABLE	20477
AlignLeft	AMT	FN_FRAME_ALIGN_HORZ_LEFT	NO DESCRIPTION AVAILABLE	20475
AlignRight	AMT	FN_FRAME_ALIGN_HORZ_RIGHT	NO DESCRIPTION AVAILABLE	20476
AlignRowBottom	AMT	FN_FRAME_ALIGN_VERT_ROW_BOTTOM	Align to Bottom of Line	20566

AlignRowTop	AMT	FN_FRAME_ALIGN_VERT_ROW_TOP	Align to Top of Line	20565
AlignTop	AMT	FN_FRAME_ALIGN_VERT_TOP	NO DESCRIPTION AVAILABLE	20478
AlignVerticalCenter	AMT	FN_FRAME_ALIGN_VERT_CENTER	Align Vertical Center	20480
AlignVerticalCharCenter	AMT	FN_FRAME_ALIGN_VERT_CHAR_CENTER	Align to Vertical Center of Character	20570
AlignVerticalRowCenter	AMT	FN_FRAME_ALIGN_VERT_ROW_CENTER	Align to Vertical Center of Line	20567
ApplyStyleDefault	AMT	FN_FORMAT_APPLY_DEFAULT	NO DESCRIPTION AVAILABLE	21757
ApplyStyleHead1	AMT	FN_FORMAT_APPLY_HEAD1	NO DESCRIPTION AVAILABLE	21754
ApplyStyleHead2	AMT	FN_FORMAT_APPLY_HEAD2	NO DESCRIPTION AVAILABLE	21755
ApplyStyleHead3	AMT	FN_FORMAT_APPLY_HEAD3	NO DESCRIPTION AVAILABLE	21756
ApplyStyleTextbody	AMT	FN_FORMAT_APPLY_TEXTBODY	NO DESCRIPTION AVAILABLE	21758
AuthoritiesEntryDialog	AMT	FN_EDIT_AUTH_ENTRY_DLG	Bibliography Entry	21833
AutoFormatApply	AMT	FN_AUTOFORMAT_APPLY	Apply	20401
AutoFormatRedlineApply	AMT	FN_AUTOFORMAT_REDLINE_APPLY	Apply and Edit Changes	20406
AutoSum	AMT	FN_TABLE_AUTOSUM	Sum	20595
BackColor	AMT	SID_ATTR_CHAR_COLOR_BACKGROUND	Highlighting	10489
BackgroundDialog	AMT	FN_FORMAT_BACKGROUND_DLG	Background	20450
BorderDialog	AMT	FN_FORMAT_BORDER_DLG	Borders	20448
BulletsAndNumberingDialog	AMT	FN_NUMBER_BULLETS	Bullets and Numbering	20121
Calc	AMT	FN_CALC_TABLE	Calculate Table	20129
CalculateSel	AMT	FN_CALCULATE	Calculate	20615
CellVertBottom	AMT	FN_TABLE_VERT_BOTTOM	Bottom	20587
CellVertCenter	AMT	FN_TABLE_VERT_CENTER	Center ( vertical )	20586
CellVertTop	AMT	FN_TABLE_VERT_NONE	Top	20585
ChainFrames	AMT	FN_FRAME_CHAIN	Link Frames	21736
ChangeDatabaseField	AMT	FN_CHANGE_DBFIELD	Exchange Database	20309
ChapterNumberingDialog	AMT	FN_NUMBERING_OUTLINE_DLG	Outline Numbering	20612
CharBackgroundExt	AMT	SID_ATTR_CHAR_COLOR_BACKGROUND_EXT	Highlight Fill	10490
CharColorExt	AMT	SID_ATTR_CHAR_COLOR_EXT	Font Color Fill	10488
CharLeftSel	AMT	FN_CHAR_LEFT_SEL	Select Character Left	20801
CharRightSel	AMT	FN_CHAR_RIGHT_SEL	Select Character Right	20802
ClosePreview	AMT	FN_CLOSE_PAGEPREVIEW	NO DESCRIPTION AVAILABLE	21254
CommentChangeTracking	AMT	FN_REDLINE_COMMENT	Comment	21827

ControlCodes	AMT	FN_VIEW_META_CHARS	Nonprinting Characters	20224
ConvertTableText	AMT	FN_CONVERT_TEXT_TABLE	Text <-> Table	20500
ConvertTableToText	AMT	FN_CONVERT_TABLE_TO_TEXT	Table to Text	20532
ConvertTextToTable	AMT	FN_CONVERT_TEXT_TO_TABLE	Text to Table	20531
CreateAbstract	AMT	FN_ABSTRACT_NEWDOC	Create AutoAbstract	21612
DecrementIndentValue	AMT	FN_DEC_INDENT_OFFSET	Decrement Indent Value	21751
DecrementLevel	AMT	FN_NUM_BULLET_DOWN	Down One Level	20130
DecrementSubLevels	AMT	FN_NUM_BULLET_OUTLINE_DOWN	Move Down with Subpoints	20139
DelLine	AMT	FN_DELETE_WHOLE_LINE	Delete Row	20935
DelToEndOfLine	AMT	FN_DELETE_LINE	Delete to End of Line	20931
DelToEndOfPara	AMT	FN_DELETE_PARA	Delete to End of Paragraph	20933
DelToEndOfSentence	AMT	FN_DELETE_SENT	Delete to End of Sentence	20927
DelToEndOfWord	AMT	FN_DELETE_WORD	Delete to End of Word	20929
DelToStartOfLine	AMT	FN_DELETE_BACK_LINE	Delete to Start of Line	20932
DelToStartOfPara	AMT	FN_DELETE_BACK_PARA	Delete to Start of Paragraph	20934
DelToStartOfSentence	AMT	FN_DELETE_BACK_SENT	Delete to Start of Sentence	20928
DelToStartOfWord	AMT	FN_DELETE_BACK_WORD	Delete to Start of Word	20930
DeleteColumns	AMT	FN_TABLE_DELETE_COL	NO DESCRIPTION AVAILABLE	20504
DeleteRows	AMT	FN_TABLE_DELETE_ROW	NO DESCRIPTION AVAILABLE	20503
DeleteTable	AMT	FN_TABLE_DELETE_TABLE	Table	20529
DistributeColumns	AMT	FN_TABLE_BALANCE_CELLS	Distribute Columns Evenly	20582
DistributeRows	AMT	FN_TABLE_BALANCE_ROWS	Distribute Rows Equally	20583
EditCurIndex	AMT	FN_EDIT_CURRENT_TOX	Edit index	21832
EditFootnote	AMT	FN_EDIT_FOOTNOTE	Footnote	20162
EditGlossary	AMT	FN_GLOSSARY_DLG	AutoText	20620
EditHyperlink	AMT	FN_EDIT_HYPERLINK	NO DESCRIPTION AVAILABLE	21835
EditRegion	AMT	FN_EDIT_REGION	Sections	20165
EndOfDocumentSel	AMT	FN_END_OF_DOCUMENT_SEL	Select to Document End	20808
EndOfLineSel	AMT	FN_END_OF_LINE_SEL	Select to End of Line	20806
EndOfParaSel	AMT	FN_END_OF_PARA_SEL	Select to Paragraph End	20820
EntireCell	AMT	FN_TABLE_SELECT_CELL	Cells	20530
EntireColumn	AMT	FN_TABLE_SELECT_COL	Select Column	20514

EntireRow	AMT	FN_TABLE_SELECT_ROW	Select Rows	20513
Escape	AMT	FN_ESCAPE	Cancel	20941
ExecHyperlinks	S	FN_STAT_HYPERLINKS	Hyperlinks Active	21186
ExecuteMacroField	AMT	FN_EXECUTE_MACROFIELD	Run Macro Field	20127
ExpandGlossary	AMT	FN_EXPAND_GLOSSARY	Run AutoText Entry	20628
FieldDialog	AMT	FN_EDIT_FIELD	Fields	20104
Fieldnames	AMT	FN_VIEW_FIELDNAME	Field Names	20226
Fields	AMT	FN_VIEW_FIELDS	Fields	20215
FlipHorizontal	AMT	FN_FLIP_HORZ_GRAFIC	Flip Vertically	20425
FlipVertical	AMT	FN_FLIP_VERT_GRAFIC	Flip Horizontally	20426
FontColor	AMT	SID_ATTR_CHAR_COLOR2	Font Color	10537
FootnoteDialog	AMT	FN_FORMAT_FOOTNOTE_DLG	Footnotes	20468
FormatColumns	AMT	FN_FORMAT_COLUMN	Columns	20453
FormatDropcap	AMT	FN_FORMAT_DROPCAPS	Drop Caps	20454
FrameDialog	AMT	FN_FORMAT_FRAME_DLG	Frame Properties	20456
GoDown	AMT	FN_LINE_DOWN	NO DESCRIPTION AVAILABLE	20904
GoLeft	AMT	FN_CHAR_LEFT	NO DESCRIPTION AVAILABLE	20901
GoRight	AMT	FN_CHAR_RIGHT	NO DESCRIPTION AVAILABLE	20902
GoToAnchor	AMT	FN_FRAME_TO_ANCHOR	Set Cursor To Anchor	20959
GoToEnd	AMT	FN_END_TABLE	To Table End	20948
GoToEndOfColumn	AMT	FN_END_OF_COLUMN	To Column End	20918
GoToEndOfDoc	AMT	FN_END_OF_DOCUMENT	To Document End	20908
GoToEndOfLine	AMT	FN_END_OF_LINE	To End of Line	20906
GoToEndOfNextColumn	AMT	FN_END_OF_NEXT_COLUMN	To End of Next Column	20952
GoToEndOfNextPage	AMT	FN_END_OF_NEXT_PAGE	To End of Next Page	20910
GoToEndOfNextPageSel	AMT	FN_END_OF_NEXT_PAGE_SEL	Select to End of Next Page	20810
GoToEndOfPage	AMT	FN_END_OF_PAGE	To Page End	20914
GoToEndOfPageSel	AMT	FN_END_OF_PAGE_SEL	Select to Page End	20814
GoToEndOfPara	AMT	FN_END_OF_PARA	To Paragraph End	20920
GoToEndOfPrevColumn	AMT	FN_END_OF_PREV_COLUMN	To Previous Column	20954
GoToEndOfPrevPage	AMT	FN_END_OF_PREV_PAGE	To End of Previous Page	20912
GoToEndOfPrevPageSel	AMT	FN_END_OF_PREV_PAGE_SEL	Select to End of Previous Page	20812

GoToNextPara	AMT	FN_NEXT_PARA	To Next Paragraph	20975
GoToNextSentence	AMT	FN_NEXT_SENT	To Next Sentence	20923
GoToNextWord	AMT	FN_NEXT_WORD	To Word Right	20921
GoToPrevPara	AMT	FN_PREV_PARA	To Previous Paragraph	20974
GoToPrevSentence	AMT	FN_PREV_SENT	To Previous Sentence	20924
GoToPrevWord	AMT	FN_PREV_WORD	To Word Left	20922
GoToStartOfColumn	AMT	FN_START_OF_COLUMN	To Column Begin	20917
GoToStartOfDoc	AMT	FN_START_OF_DOCUMENT	To Document Begin	20907
GoToStartOfLine	AMT	FN_START_OF_LINE	To Line Begin	20905
GoToStartOfNextColumn	AMT	FN_START_OF_NEXT_COLUMN	To Begin of Next Column	20951
GoToStartOfNextPage	AMT	FN_START_OF_NEXT_PAGE	To Begin of Next Page	20909
GoToStartOfNextPageSel	AMT	FN_START_OF_NEXT_PAGE_SEL	Select to Begin of Next Page	20809
GoToStartOfPage	AMT	FN_START_OF_PAGE	To Page Begin	20913
GoToStartOfPageSel	AMT	FN_START_OF_PAGE_SEL	Select to Page Begin	20813
GoToStartOfPara	AMT	FN_START_OF_PARA	To Paragraph Begin	20919
GoToStartOfPrevColumn	AMT	FN_START_OF_PREV_COLUMN	To Begin of Previous Column	20953
GoToStartOfPrevPage	AMT	FN_START_OF_PREV_PAGE	To Begin of Previous Page	20911
GoToStartOfPrevPageSel	AMT	FN_START_OF_PREV_PAGE_SEL	Select to Begin of Previous Page	20811
GoToStartOfTable	AMT	FN_START_TABLE	To Table Begin	20947
GoUp	AMT	FN_LINE_UP	NO DESCRIPTION AVAILABLE	20903
GotoNextIndexMark	AMT	FN_NEXT_TOXMARK	Go to Next Index Mark	20983
GotoNextInputField	AMT	FN_GOTO_NEXT_INPUTFLD	To Next Input Field	20147
GotoNextObject	AMT	FN_GOTO_NEXT_OBJ	To Next Object	20944
GotoNextPlacemark	AMT	FN_GOTO_NEXT_MARK	To Next Placeholder	20976
GotoNextSentenceSel	AMT	FN_NEXT_SENT_SEL	Select to Next Sentence	20823
GotoNextTableFormula	AMT	FN_NEXT_TBLFML	Go to next table formula	20985
GotoNextWrongTableFormula	AMT	FN_NEXT_TBLFML_ERR	Go to next faulty table formula	20987
GotoPage	AMT	FN_NAVIGATION_PI_GOTO_PAGE	To Page	20659
GotoPrevIndexMark	AMT	FN_PREV_TOXMARK	Go to Previous Index Mark	20984
GotoPrevInputField	AMT	FN_GOTO_PREV_INPUTFLD	To Previous Input Field	20148
GotoPrevObject	AMT	FN_GOTO_PREV_OBJ	To Previous Object	20945
GotoPrevPlacemark	AMT	FN_GOTO_PREV_MARK	To Previous Placeholder	20977

GotoPrevSentenceSel	AMT	FN_PREV_SENT_SEL	Select to Previous Sentence	20824
GotoPrevTableFormula	AMT	FN_PREV_TBLFML	Go to previous table formula	20986
GotoPrevWrongTableFormula	AMT	FN_PREV_TBLFML_ERR	Go to previous faulty table formula	20988
Graphic	AMT	FN_VIEW_GRAPHIC	Graphics On/Off	20213
GraphicDialog	AMT	FN_FORMAT_GRAFIG_DLG	Picture	20458
Grow	AMT	FN_GROW_FONT_SIZE	Increase Font	20403
HScroll	AMT	FN_HSCROLLBAR	Scroll Horizontal	20218
HeadingRowsRepeat	AMT	FN_TABLE_HEADLINE_REPEAT	Heading rows repeat	20520
Hyphenate	AMT	FN_HYPHENATE_OPT_DLG	NO DESCRIPTION AVAILABLE	20605
IncrementIndentValue	AMT	FN_INC_INDENT_OFFSET	Increment Indent Value	21750
IncrementLevel	AMT	FN_NUM_BULLET_UP	Up One Level	20131
IncrementSubLevels	AMT	FN_NUM_BULLET_OUTLINE_UP	Move Up with Subpoints	20140
IndexEntryDialog	AMT	FN_EDIT_IDX_ENTRY_DLG	Index Entry	20123
IndexMarkToIndex	AMT	FN_IDX_MARK_TO_IDX	Index Mark to Index	20962
InsertAnnotation	AMT	FN_POSTIT	NO DESCRIPTION AVAILABLE	20329
InsertAuthorField	AMT	FN_INSERT_FLD_AUTHOR	NO DESCRIPTION AVAILABLE	20398
InsertAuthoritiesEntry	AMT	FN_INSERT_AUTH_ENTRY_DLG	Bibliography Entry	21421
InsertBookmark	AMT	FN_INSERT_BOOKMARK	Bookmark	20302
InsertBreak	AMT	FN_INSERT_BREAK_DLG	Manual Break	20304
InsertCaptionDialog	AMT	FN_INSERT_CAPTION	Caption	20310
InsertColumnBreak	AMT	FN_INSERT_COLUMN_BREAK	NO DESCRIPTION AVAILABLE	20305
InsertColumns	AMT	FN_TABLE_INSERT_COL	NO DESCRIPTION AVAILABLE	20502
InsertCtrl	AMT	FN_INSERT_CTRL	NO DESCRIPTION AVAILABLE	20389
InsertDateField	AMT	FN_INSERT_FLD_DATE	Date	20392
InsertEndnote	AMT	FN_INSERT_ENDNOTE	Insert Endnote Directly	21418
InsertEnvelope	AMT	FN_ENVELOP	Envelope	21050
InsertField	AMT	FN_INSERT_FIELD	Other	20308
InsertFieldCtrl	AMT	FN_INSERT_FIELD_CTRL	Insert Fields	20391
InsertFootnote	AMT	FN_INSERT_FOOTNOTE	Insert Footnote Directly	20399
InsertFootnoteDialog	AMT	FN_INSERT_FOOTNOTE_DLG	Footnote	20312
InsertFormula	AMT	FN_EDIT_FORMULA	Formula	20128
InsertFrame	AMT	FN_INSERT_FRAME	Frame	20334

InsertFrameInteract	AMT	FN_INSERT_FRAME_INTERACT	Insert Frame Manually	20333
InsertFrameInteractNoColumns	AMT	FN_INSERT_FRAME_INTERACT_NOCOL	Insert single-column frame manually	20336
InsertGraphicRuler	AMT	FN_INSERT_HRULER	Horizontal Ruler	21411
InsertHardHyphen	AMT	FN_INSERT_HARDHYPHEN	Insert Non-breaking Hyphen	20385
InsertHyperlinkDlg	AMT	FN_INSERT_HYPERLINK	Insert Hyperlink	20314
InsertIndexesEntry	AMT	FN_INSERT_IDX_ENTRY_DLG	Entry	20335
InsertLinebreak	AMT	FN_INSERT_LINEBREAK	Insert Manual Row Break	20318
InsertMultiIndex	AMT	FN_INSERT_MULTI_TOX	Indexes and Tables	21420
InsertNeutralParagraph	AMT	FN_NUM_BULLET_NONUM	Insert Unnumbered Entry	20136
InsertNonBreakingSpace	AMT	FN_INSERT_HARD_SPACE	Insert Non-breaking Space	20344
InsertObjCtrl	AMT	FN_INSERT_OBJ_CTRL	Insert Object	20390
InsertObjectDialog	AMT	FN_INSERT_OBJECT_DLG	Insert Other Objects	20322
InsertObjectStarMath	AMT	FN_INSERT_SMA	NO DESCRIPTION AVAILABLE	20369
InsertPageCountField	AMT	FN_INSERT_FLD_PGCOUNT	Page Count	20395
InsertPageFooter	AMT	FN_INSERT_PAGEFOOTER	Footer	21414
InsertPageHeader	AMT	FN_INSERT_PAGEHEADER	Header	21413
InsertPageNumberField	AMT	FN_INSERT_FLD_PGNUMBER	Page Number	20394
InsertPagebreak	AMT	FN_INSERT_PAGEBREAK	Insert Manual Page Break	20323
InsertPara	AMT	FN_INSERT_BREAK	Insert Paragraph	20303
InsertReferenceField	AMT	FN_INSERT_REF_FIELD	Cross-reference	20313
InsertRows	AMT	FN_TABLE_INSERT_ROW	NO DESCRIPTION AVAILABLE	20501
InsertScript	AMT	FN_JAVAEDIT	Script	21410
InsertSection	AMT	FN_INSERT_REGION	Section	21419
InsertSoftHyphen	AMT	FN_INSERT_SOFT_HYPHEN	Insert Optional Hyphen	20343
InsertSymbol	AMT	FN_INSERT_SYMBOL	NO DESCRIPTION AVAILABLE	20328
InsertTable	AMT	FN_INSERT_TABLE	Table	20330
InsertTimeField	AMT	FN_INSERT_FLD_TIME	NO DESCRIPTION AVAILABLE	20393
InsertTitleField	AMT	FN_INSERT_FLD_TITLE	Title	20397
InsertTopicField	AMT	FN_INSERT_FLD_TOPIC	Subject	20396
JumpDownThisLevel	AMT	FN_NUM_BULLET_NEXT	To Next Paragraph in Level	20133
JumpToEndOfDoc	AMT	FN_END_DOC_DIRECT	Directly to Document End	20979
JumpToFooter	AMT	FN_TO_FOOTER	To Footer	20961



JumpToFootnoteArea	AMT	FN_TO_FOOTNOTE_AREA	Edit Footnote/Endnote	20963
JumpToFootnoteOrAnchor	AMT	FN_FOOTNOTE_TO_ANCHOR	To Footnote Anchor	20955
JumpToHeader	AMT	FN_TO_HEADER	To Header	20960
JumpToNextBookmark	AMT	FN_NEXT_BOOKMARK	To Next Bookmark	20168
JumpToNextFootnote	AMT	FN_NEXT_FOOTNOTE	To Next Footnote	20956
JumpToNextFrame	AMT	FN_CNTNT_TO_NEXT_FRAME	To Next Frame	20958
JumpToNextRegion	AMT	FN_GOTO_NEXT_REGION	To Next Section	21609
JumpToNextTable	AMT	FN_NEXT_TABLE	NO DESCRIPTION AVAILABLE	20949
JumpToPrevBookmark	AMT	FN_PREV_BOOKMARK	To Previous Bookmark	20169
JumpToPrevFootnote	AMT	FN_PREV_FOOTNOTE	To Previous Footnote	20957
JumpToPrevRegion	AMT	FN_GOTO_PREV_REGION	To Previous Section	21610
JumpToPrevTable	AMT	FN_PREV_TABLE	NO DESCRIPTION AVAILABLE	20950
JumpToReference	AMT	FN_GOTO_REFERENCE	To Reference	20166
JumpToStartOfDoc	AMT	FN_START_DOC_DIRECT	Directly to Document Begin	20978
JumpUpThisLevel	AMT	FN_NUM_BULLET_PREV	To Previous Paragraph in Level	20132
LineDownSel	AMT	FN_LINE_DOWN_SEL	Select Down	20804
LineNumberingDialog	AMT	FN_LINE_NUMBERING_DLG	Line Numbering	20602
LineUpSel	AMT	FN_LINE_UP_SEL	Select to Top Line	20803
LinkDialog	AMT	FN_EDIT_LINK_DLG	Links	20109
LoadStyles	AMT	SID_TEMPLATE_LOAD	Load Styles	5663
MailMergeWizard	AMT	FN_MAILMERGE_WIZARD	Mail Merge Wizard	20364
Marks	AMT	FN_VIEW_MARKS	Field Shadings	20225
MergeCells	AMT	FN_TABLE_MERGE_CELLS	NO DESCRIPTION AVAILABLE	20506
MergeDialog	AMT	FN_QRY_MERGE	Mail Merge	20367
MergeTable	AMT	FN_TABLE_MERGE_TABLE	Merge Table	21752
MirrorGraphicOnEvenPages	AMT	FN_GRAPHIC_MIRROR_ON_EVEN_PAGES	Flip Graphics on Even Pages	21741
MirrorOnEvenPages	AMT	FN_FRAME_MIRROR_ON_EVEN_PAGES	Mirror Object on Even Pages	21740
MoveDown	AMT	FN_NUM_BULLET_MOVEDOWN	Move Down	20135
MoveDownSubItems	AMT	FN_NUM_BULLET_OUTLINE_MOVEDOWN	Move Down with Subpoints	20142
MoveUp	AMT	FN_NUM_BULLET_MOVEUP	Move Up	20134
MoveUpSubItems	AMT	FN_NUM_BULLET_OUTLINE_MOVEUP	Move Up with Subpoints	20141
NameGroup	AMT	FN_NAME_GROUP	NO DESCRIPTION AVAILABLE	21614

NewGlobalDoc	AMT	FN_NEW_GLOBAL_DOC	Create Master Document	20004
NewHtmlDoc	AMT	FN_NEW_HTML_DOC	Create HTML Document	20040
NumberFormatCurrency	AMT	FN_NUMBER_CURRENCY	NO DESCRIPTION AVAILABLE	21727
NumberFormatDate	AMT	FN_NUMBER_DATE	NO DESCRIPTION AVAILABLE	21725
NumberFormatDecimal	AMT	FN_NUMBER_TWODEC	NO DESCRIPTION AVAILABLE	21723
NumberFormatPercent	AMT	FN_NUMBER_PERCENT	NO DESCRIPTION AVAILABLE	21728
NumberFormatScientific	AMT	FN_NUMBER_SCIENTIFIC	NO DESCRIPTION AVAILABLE	21724
NumberFormatStandard	AMT	FN_NUMBER_STANDARD	NO DESCRIPTION AVAILABLE	21721
NumberFormatTime	AMT	FN_NUMBER_TIME	NO DESCRIPTION AVAILABLE	21726
NumberOrNoNumber	AMT	FN_NUM_OR_NONUM	Numbering On/Off	20146
NumberingStart	AMT	FN_NUMBER_NEWSTART	Restart Numbering	21738
ObjectBackOne	AMT	FN_FRAME_UP	NO DESCRIPTION AVAILABLE	20522
ObjectForwardOne	AMT	FN_FRAME_DOWN	NO DESCRIPTION AVAILABLE	20523
OnlineAutoFormat	AMT	FN_AUTOFORMAT_AUTO	While Typing	20402
OptimizeTable	AMT	FN_OPTIMIZE_TABLE	Optimize	20510
PageColumnDialog	AMT	FN_FORMAT_PAGE_COLUMN_DLG	Page Columns	20449
PageDialog	AMT	FN_FORMAT_PAGE_DLG	Page Settings	20452
PageDown	AMT	FN_PAGEDOWN	Next Page	20938
PageDownSel	AMT	FN_PAGEDOWN_SEL	Select to Next Page	20830
PageOffset	AMT	FN_CHANGE_PAGENUM	NO DESCRIPTION AVAILABLE	20634
PageStyleApply	AMT	FN_SET_PAGE_STYLE	Apply Page Style	20493
PageStyleName	S	FN_STAT_TEMPLATE	Page Style	21182
PageUp	AMT	FN_PAGEUP	Previous Page	20937
PageUpSel	AMT	FN_PAGEUP_SEL	Select to Previous Page	20829
PasteSpecial	AMT	FN_PASTESPECIAL	NO DESCRIPTION AVAILABLE	20114
PreviewPrintOptions	AMT	FN_PREVIEW_PRINT_OPTIONS	Print options page view	20250
PreviewZoom	AMT	FN_PREVIEW_ZOOM	Preview Zoom	20251
PrintLayout	AMT	FN_PRINT_LAYOUT	Print Layout	20237
PrintPagePreView	AMT	FN_PRINT_PAGEPREVIEW	Print page view	21253
Protect	AMT	FN_TABLE_SET_READ_ONLY_CELLS	NO DESCRIPTION AVAILABLE	20517
ProtectTraceChangeMode	AMT	FN_REDLINE_PROTECT	NO DESCRIPTION AVAILABLE	21823
RefreshView	AMT	FN_REFRESH_VIEW	Restore View	20201

RemoveBullets	AMT	FN_NUM_BULLET_OFF	Numbering Off	20137
RemoveDirectCharFormats	AMT	FN_REMOVE_DIRECT_CHAR_FORMATS	Remove Direct Character Formats	21759
RemoveTableOf	AMT	FN_REMOVE_CUR_TOX	Delete index	20655
Repaginate	AMT	FN_REPAGINATE	Page Formatting	20161
RepeatSearch	AMT	FN_REPEAT_SEARCH	NO DESCRIPTION AVAILABLE	20150
ResetAttributes	AMT	FN_FORMAT_RESET	NO DESCRIPTION AVAILABLE	20469
ResetTableProtection	AMT	FN_TABLE_UNSET_READ_ONLY	Unprotect sheet	20559
RowSplit	AMT	FN_TABLE_ROW_SPLIT	Allow Row to Break Across Pages and Columns	21753
Ruler	AMT	FN_RULER	Ruler	20211
SelectTable	AMT	FN_TABLE_SELECT_ALL	Select Table	20515
SelectText	AMT	FN_SELECT_PARA	Select Paragraph	20197
SelectTextMode	AMT	FN_READONLY_SELECTION_MODE	Select Text	20989
SelectWord	AMT	FN_SELECT_WORD	Select Word	20943
SelectionMode	S	FN_STAT_SELMODE	Selection Mode	21185
SendAbstractToStarImpress	AMT	FN_ABSTRACT_STARIMPRESS	AutoAbstract to Presentation	21613
SendOutlineToClipboard	AMT	FN_OUTLINE_TO_CLIPBOARD	Outline to Clipboard	20037
SendOutlineToStarImpress	AMT	FN_OUTLINE_TO_IMPRESS	Outline to Presentation	20036
SetAnchorAtChar	AMT	FN_TOOL_ANKER_AT_CHAR	Anchor to Character	21412
SetAnchorToChar	AMT	FN_TOOL_ANKER_CHAR	Anchor as Character	20384
SetAnchorToFrame	AMT	FN_TOOL_ANKER_FRAME	Anchor To Frame	20366
SetAnchorToPage	AMT	FN_TOOL_ANKER_PAGE	NO DESCRIPTION AVAILABLE	20350
SetAnchorToPara	AMT	FN_TOOL_ANKER_PARAGRAPH	Anchor To Paragraph	20351
SetExtSelection	AMT	FN_SET_EXT_MODE	Extended Selection On	20940
SetMultiSelection	AMT	FN_SET_ADD_MODE	MultiSelection On	20939
SetOptimalColumnWidth	AMT	FN_TABLE_ADJUST_CELLS	NO DESCRIPTION AVAILABLE	20521
SetOptimalRowHeight	AMT	FN_TABLE_OPTIMAL_HEIGHT	NO DESCRIPTION AVAILABLE	20528
SetRowHeight	AMT	FN_TABLE_SET_ROW_HEIGHT	Row Height	20507
ShadowCursor	AMT	FN_SHADOWCURSOR	Direct Cursor On/Off	22204
ShiftBackspace	AMT	FN_SHIFT_BACKSPACE	Backspace	20942
ShowBookview	AMT	FN_SHOW_BOOKVIEW	Book Preview	21255
ShowHiddenParagraphs	AMT	FN_VIEW_HIDDEN_PARA	Hidden Paragraphs	20242
ShowMultiplePages	AMT	FN_SHOW_MULTIPLE_PAGES	Page Preview: Multiple Pages	21252

ShowTrackedChanges	AMT	FN_REDLINE_SHOW	Show	21826
ShowTwoPages	AMT	FN_SHOW_TWO_PAGES	Page Preview: Two Pages	21251
Shrink	AMT	FN_SHRINK_FONT_SIZE	Reduce Font	20404
SortDialog	AMT	FN_SORTING_DLG	Sort	20614
SplitCell	AMT	FN_TABLE_SPLIT_CELLS	NO DESCRIPTION AVAILABLE	20505
SplitTable	AMT	FN_TABLE_SPLIT_TABLE	Split Table	21742
StartAutoCorrect	AMT	FN_AUTO_CORRECT	AutoCorrect	20649
StartOfDocumentSel	AMT	FN_START_OF_DOCUMENT_SEL	Select to Document Begin	20807
StartOfLineSel	AMT	FN_START_OF_LINE_SEL	Select to Begin of Line	20805
StartOfParaSel	AMT	FN_START_OF_PARA_SEL	Select to Paragraph Begin	20819
StatePageNumber	S	FN_STAT_PAGE	Page Number	21181
SubScript	AMT	FN_SET_SUB_SCRIPT	NO DESCRIPTION AVAILABLE	20412
SuperScript	AMT	FN_SET_SUPER_SCRIPT	NO DESCRIPTION AVAILABLE	20411
SwBackspace	AMT	FN_BACKSPACE	Backspace	20926
SwitchXFormsDesignMode	AMT	FN_XFORMS_DESIGN_MODE	NO DESCRIPTION AVAILABLE	22300
TableBoundaries	AMT	FN_VIEW_TABLEGRID	Table Boundaries	20227
TableDialog	AMT	FN_FORMAT_TABLE_DLG	Table Properties	20460
TableModeFix	AMT	FN_TABLE_MODE_FIX	Table: Fixed	20589
TableModeFixProp	AMT	FN_TABLE_MODE_FIX_PROP	Table: Fixed, Proportional	20590
TableModeVariable	AMT	FN_TABLE_MODE_VARIABLE	Table: Variable	20591
TableNumberFormatDialog	AMT	FN_NUM_FORMAT_TABLE_DLG	Number Format	20445
TableNumberRecognition	AMT	FN_SET_MODOPT_TBLNUMFMT	Number Recognition	20252
TableSort	AMT	FN_TABLE_SORT_DIALOG	Sort	20533
TextAttributes	AMT	FN_DRAWTEXT_ATTR_DLG	NO DESCRIPTION AVAILABLE	20376
TextWrap	AMT	FN_DRAW_WRAP_DLG	Text Wrap	20203
ThesaurusDialog	AMT	FN_THESAURUS_DLG	Thesaurus	20603
ToggleAnchorType	AMT	FN_TOOL_ANKER	NO DESCRIPTION AVAILABLE	20349
ToggleObjectLayer	AMT	FN_TOOL_HIERARCHIE	Change Position	20352
TrackChanges	AMT	FN_REDLINE_ON	Record	21825
UnderlineDouble	AMT	FN_UNDERLINE_DOUBLE	NO DESCRIPTION AVAILABLE	20405
UnhainFrames	AMT	FN_FRAME_UNCHAIN	Unlink Frames	21737
UnsetCellsReadOnly	AMT	FN_TABLE_UNSET_READ_ONLY_CELLS	Unprotect cells	20519

UpdateAll	AMT	FN_UPDATE_ALL	Update All	21828
UpdateAllIndexes	AMT	FN_UPDATE_TOX	All Indexes and Tables	20653
UpdateAllLinks	AMT	FN_UPDATE_ALL_LINKS	Links	21824
UpdateCharts	AMT	FN_UPDATE_CHARTS	All Charts	21834
UpdateCurIndex	AMT	FN_UPDATE_CUR_TOX	Current Index	20654
UpdateFields	AMT	FN_UPDATE_FIELDS	Fields	20126
UpdateInputFields	AMT	FN_UPDATE_INPUTFIELDS	Update Input Fields	20143
VRuler	AMT	FN_VLINEAL	Vertical Ruler	20216
VScroll	AMT	FN_VSCROLLBAR	Vertical Scroll Bar	20217
ViewBounds	AMT	FN_VIEW_BOUNDS	Text Boundaries	20214
WordCountDialog	AMT	FN_WORDCOUNT_DIALOG	Word Count	22298
WordLeftSel	AMT	FN_PREV_WORD_SEL	Select to Begin of Word	20822
WordRightSel	AMT	FN_NEXT_WORD_SEL	Select to Word Right	20821
WrapAnchorOnly	AMT	FN_WRAP_ANCHOR_ONLY	Wrap First Paragraph	20581
WrapContour	AMT	FN_FRAME_WRAP_CONTOUR	Wrap Contour On	20584
WrapIdeal	AMT	FN_FRAME_WRAP_IDEAL	Optimal Page Wrap	20563
WrapLeft	AMT	FN_FRAME_WRAP_LEFT	Wrap Left	20572
WrapOff	AMT	FN_FRAME_NOWRAP	Wrap Off	20472
WrapOn	AMT	FN_FRAME_WRAP	Page Wrap	20473
WrapRight	AMT	FN_FRAME_WRAP_RIGHT	Wrap Right	20573
WrapThrough	AMT	FN_FRAME_WRAPTHRU	Wrap Through	20474
WrapThroughTransparent	AMT	FN_FRAME_WRAPTHRU_TRANSP	In Background	20564

## Calc commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
AcceptChanges	AMT	FID_CHG_ACCEPT	Accept or Reject	26258
Add	AMT	FID_TAB_APPEND	Append Sheet	26350
AddPrintArea	AMT	SID_ADD_PRINTAREA	Add	26651
AdjustPrintZoom	AMT	FID_ADJUST_PRINTZOOM	Adjust Scale	26652

AlignBlock	AMT	SID_ALIGNBLOCK	Justified	26374
AlignBottom	AMT	SID_ALIGNBOTTOM	Align Bottom	26376
AlignHorizontalCenter	AMT	SID_ALIGNCENTERHOR	Align Center Horizontally	26373
AlignLeft	AMT	SID_ALIGNLEFT	Align Left	26371
AlignRight	AMT	SID_ALIGNRIGHT	Align Right	26372
AlignTop	AMT	SID_ALIGNTOP	Align Top	26375
AlignVCenter	AMT	SID_ALIGNCENTERVER	Align Center Vertically	26377
ApplyNames	AMT	FID_APPLY_NAME	Assign Names	26274
AuditingFillMode	AMT	SID_DETECTIVE_FILLMODE	Fill Mode	26462
AutoComplete	AMT	FID_AUTOCOMplete	AutoInput	26319
AutoFill	AMT	FID_FILL_AUTO	AutoFill Data Series: automatic	26556
AutoOutline	AMT	SID_AUTO_OUTLINE	AutoOutline	26333
AutoRefreshArrows	AMT	SID_DETECTIVE_AUTO	AutoRefresh	26471
AutomaticCalculation	AMT	FID_AUTO_CALC	AutoCalculate	26303
Calculate	AMT	FID_RECALC	Recalculate	26304
CalculateHard	AMT	FID_HARD_RECALC	Recalculate Hard	26318
Cancel	AMT	SID_CANCEL	Cancel	26557
ChooseDesign	AMT	SID_CHOOSE_DESIGN	Choose Themes	26082
ClearArrowDependents	AMT	SID_DETECTIVE_DEL_SUCC	Remove Dependents	26459
ClearArrowPrecedents	AMT	SID_DETECTIVE_DEL_PRED	Remove Precedents	26457
ClearArrows	AMT	SID_DETECTIVE_DEL_ALL	Remove All Traces	26461
ClearContents	AMT	SID_DELETE_CONTENTS	Delete Contents	26553
ClosePreview	AMT	SID_PREVIEW_CLOSE	Close Preview	26503
ColumnWidth	AMT	FID_COL_WIDTH	Width	26285
CommentChange	AMT	FID_CHG_COMMENT	Comments	26259
ConditionalFormatDialog	AMT	SID_OPENDLG_CONDFRMT	Conditional Formatting	26159
CreateNames	AMT	FID_USE_NAME	Create	26273
DataAreaRefresh	AMT	SID_REFRESH_DBAREA	Refresh Range	26643
DataConsolidate	AMT	SID_OPENDLG_CONSOLIDATE	Consolidate	26150
DataDataPilotRun	AMT	SID_OPENDLG_PIVOTTABLE	Start	26151
DataFilterAutoFilter	AMT	SID_AUTO_FILTER	AutoFilter	26325
DataFilterHideAutoFilter	AMT	SID_AUTOFILTER_HIDE	Hide AutoFilter	26341

DataFilterRemoveFilter	AMT	SID_UNFILTER	Remove Filter	26326
DataFilterSpecialFilter	AMT	SID_SPECIAL_FILTER	Advanced Filter	26324
DataFilterStandardFilter	AMT	SID_FILTER	Standard Filter	26323
DataImport	AMT	SID_IMPORT_DATA	Import Data	26335
DataPilotFilter	AMT	SID_DP_FILTER	DataPilot Filter	26091
DataReImport	AMT	SID_REIMPORT_DATA	Refresh Data Import	26336
DataSelect	AMT	SID_DATA_SELECT	Selection List	26610
DataSort	AMT	SID_SORT	Sort	26322
DataSubTotals	AMT	SID_SUBTOTALS	Subtotals	26328
DefineDBName	AMT	SID_DEFINE_DBNAME	Define Range	26320
DefineLabelRange	AMT	SID_DEFINE_COLROWNAMERANGES	Labels	26629
DefineName	AMT	FID_DEFINE_NAME	Define	26271
DefinePrintArea	AMT	SID_DEFINE_PRINTAREA	Define	26602
DeleteAllBreaks	AMT	FID_DEL_MANUALBREAKS	Delete Page Breaks	26650
DeleteCell	AMT	FID_DELETE_CELL	Delete Cells	26222
DeleteColumnbreak	AMT	FID_DEL_COLBRK	Column Break	26264
DeleteColumns	AMT	SID_DEL_COLS	Delete Columns	26237
DeletePivotTable	AMT	SID_PIVOT_KILL	Delete	26315
DeletePrintArea	AMT	SID_DELETE_PRINTAREA	Remove	26603
DeleteRowbreak	AMT	FID_DEL_ROWBRK	Row Break	26263
DeleteRows	AMT	SID_DEL_ROWS	Delete Rows	26236
Deselect	AMT	SID_SELECT_NONE	Undo Selection	26549
DrawChart	AMT	SID_DRAW_CHART	Insert Chart	26071
EditHeaderAndFooter	AMT	SID_HFEDIT	Headers & Footers	26235
EditLinks	AMT	SID_LINKS	Links	26060
EditPrintArea	AMT	SID_OPENDLG_EDIT_PRINTAREA	Edit	26605
EuroConverter	AMT	SID_EURO_CONVERTER	Euro Converter	26083
FillDown	AMT	FID_FILL_TO_BOTTOM	Down	26224
FillLeft	AMT	FID_FILL_TO_LEFT	Left	26227
FillRight	AMT	FID_FILL_TO_RIGHT	Right	26225
FillSeries	AMT	FID_FILL_SERIES	Series	26229
FillTable	AMT	FID_FILL_TAB	Sheet	26228

FillUp	AMT	FID_FILL_TO_TOP	Up	26226
FirstPage	AMT	SID_PREVIEW_FIRST	First Page	26498
FocusCellAddress	AMT	FID_FOCUS_POSWND	Sheet Area Input Field	26645
FocusInputLine	AMT	SID_FOCUS_INPUTLINE	Input Line	26089
FormatCellDialog	AMT	FID_CELL_FORMAT	Cells	26280
FreezePanels	AMT	SID_WINDOW_FIX	Freeze	26070
FunctionBox	AMT	FID_FUNCTION_BOX	Function List	26248
FunctionDialog	AMT	SID_OPENDLG_FUNCTION	Function	26152
GoDownToEndOfData	AMT	SID_CURSORBLKDOWN	To Lower Block Margin	26536
GoDownToEndOfDataSel	AMT	SID_CURSORBLKDOWN_SEL	Select to Lower Block Margin	26540
GoLeftBlock	AMT	SID_CURSORPAGELEFT_	NO DESCRIPTION AVAILABLE	26527
GoLeftToStartOfData	AMT	SID_CURSORBLKLEFT	To Left Block Margin	26537
GoLeftToStartOfDataSel	AMT	SID_CURSORBLKLEFT_SEL	Select to Left Block Margin	26541
GoRightBlock	AMT	SID_CURSORPAGERIGHT_	Page Right	26529
GoRightBlockSel	AMT	SID_CURSORPAGERIGHT_SEL	Select to Page Right	26530
GoRightToEndOfData	AMT	SID_CURSORBLKRIGHT	To Right Block Margin	26538
GoRightToEndOfDataSel	AMT	SID_CURSORBLKRIGHT_SEL	Select to Right Block Margin	26542
GoToCurrentCell	AMT	SID_ALIGNCURSOR	To Current Cell	26550
GoUpToStartOfData	AMT	SID_CURSORBLKUP	To Upper Block Margin	26535
GoUpToStartOfDataSel	AMT	SID_CURSORBLKUP_SEL	Select to Upper Block Margin	26539
GoalSeekDialog	AMT	SID_OPENDLG_SOLVE	Goal Seek	26153
Hide	AMT	FID_TABLE_HIDE	Hide	26289
HideColumn	AMT	FID_COL_HIDE	Hide	26287
HideRow	AMT	FID_ROW_HIDE	Hide	26283
Hyphenate	AMT	SID_ENABLE_HYPHENATION	Hyphenation	26087
InputLineVisible	AMT	FID_TOGGLEINPUTLINE	Formula Bar	26241
InsCellsCtrl	AMT	SID_TBXCTL_INSCELLS	Insert Cells	26627
InsObjCtrl	AMT	SID_TBXCTL_INSOBJ	Insert Object	26628
Insert	AMT	FID_INS_TABLE	Sheet	26269
InsertCell	AMT	FID_INS_CELL	Cells	26266
InsertCellsDown	AMT	FID_INS_CELLSDOWN	Insert Cells Down	26278
InsertCellsRight	AMT	FID_INS_CELLSRIGHT	Insert Cells Right	26279



InsertColumnBreak	AMT	FID_INS_COLBRK	Column Break	26262
InsertColumns	AMT	FID_INS_COLUMN	Insert Columns	26268
InsertContents	AMT	FID_INS_CELL_CONTENTS	Paste Special	26265
InsertCtrl	AMT	SID_TBXCTL_INSERT	Insert	26626
InsertExternalDataSource	AMT	SID_EXTERNAL_SOURCE	Link to External Data	26085
InsertName	AMT	FID_INSERT_NAME	Insert	26272
InsertObjectStarImage	AMT	SID_INSERT_SIMAGE	Insert From Image Editor	26061
InsertObjectStarMath	AMT	SID_INSERT_SMATH	Formula	26063
InsertRowBreak	AMT	FID_INS_ROWBRK	Row Break	26261
InsertRows	AMT	FID_INS_ROW	Insert Rows	26267
InsertSheetFromFile	AMT	FID_INS_TABLE_EXT	Sheet From File	26275
JumpToNextTable	AMT	SID_NEXT_TABLE	To Next Sheet	26543
JumpToNextTableSel	AMT	SID_NEXT_TABLE_SEL	Select to Next Sheet	26561
JumpToNextUnprotected	AMT	SID_NEXT_UNPROTECT	To Next Unprotected Cell	26545
JumpToPrevTable	AMT	SID_PREV_TABLE	To Previous Sheet	26544
JumpToPrevTableSel	AMT	SID_PREV_TABLE_SEL	Select to Previous Sheet	26562
JumpToPreviousUnprotected	AMT	SID_PREV_UNPROTECT	To Previous Unprotected Cell	26546
LastPage	AMT	SID_PREVIEW_LAST	Last Page	26499
MergeCells	AMT	FID_MERGE_ON	Merge Cells	26293
Move	AMT	FID_TAB_MOVE	Move/Copy	26348
Name	AMT	FID_TAB_RENAME	Rename Sheet	26347
NextPage	AMT	SID_PREVIEW_NEXT	Next Page	26496
NormalViewMode	AMT	FID_NORMALVIEWMODE	Normal	26249
NoteVisible	AMT	FID_NOTE_VISIBLE	Show Note	26630
NumberFormatCurrency	AMT	SID_NUMBER_CURRENCY	Number Format: Currency	26045
NumberFormatDate	AMT	SID_NUMBER_DATE	Number Format : Date	26053
NumberFormatDecDecimals	AMT	SID_NUMBER_DECDEC	Number Format: Delete Decimal Place	26058
NumberFormatDecimal	AMT	SID_NUMBER_TWODEC	Number Format: Decimal	26054
NumberFormatIncDecimals	AMT	SID_NUMBER_INCDEC	Number Format: Add Decimal Place	26057
NumberFormatPercent	AMT	SID_NUMBER_PERCENT	Number Format: Percent	26046
NumberFormatScientific	AMT	SID_NUMBER_SCIENTIFIC	Number Format: Exponential	26055
NumberFormatStandard	AMT	SID_NUMBER_STANDARD	Number Format: Standard	26052

NumberFormatTime	AMT	SID_NUMBER_TIME	Number Format: Time	26056
ObjectMirrorHorizontal	AMT	SID_MIRROR_HORIZONTAL	Flip Object Horizontally	26066
ObjectMirrorVertical	AMT	SID_MIRROR_VERTICAL	Flip Vertically	26065
PageFormatDialog	AMT	SID_FORMATPAGE	Page	26295
PagebreakMode	AMT	FID_PAGEBREAKMODE	Page Break Preview	26247
PasteSpecial	AMT	FID_PASTE_CONTENTS	NO DESCRIPTION AVAILABLE	26220
PreviousPage	AMT	SID_PREVIEW_PREVIOUS	Previous Page	26497
Protect	AMT	FID_PROTECT_TABLE	Sheet	26306
ProtectTraceChangeMode	AMT	SID_CHG_PROTECT	Protect Records	26084
RecalcPivotTable	AMT	SID_PIVOT_RECALC	Refresh	26314
RefreshArrows	AMT	SID_DETECTIVE_REFRESH	Refresh Traces	26470
Remove	AMT	FID_DELETE_TABLE	Delete	26223
RenameObject	AMT	SID_RENAME_OBJECT	Name Object	26088
RenameTable	AMT	FID_TAB_MENU_RENAME	Rename	26346
RepeatSearch	AMT	FID_REPEAT_SEARCH	Repeat Search	26612
ResetAttributes	AMT	SID_CELL_FORMAT_RESET	Default Formatting	26067
ResetPrintZoom	AMT	FID_RESET_PRINTZOOM	Reset Scale	26653
RowHeight	AMT	FID_ROW_HEIGHT	Height	26281
Scale	AMT	FID_SCALE	Scale Screen Display	26244
ScenarioManager	AMT	SID_SCENARIOS	Scenarios	26312
SelectArrayFormula	AMT	SID_MARKARRAYFORMULA	Select Array Formula	26560
SelectColumn	AMT	SID_SELECT_COL	Select Column	26547
SelectDB	AMT	SID_SELECT_DB	Select Range	26321
SelectData	AMT	SID_MARKDATAAREA	Select Data Area	26551
SelectRow	AMT	SID_SELECT_ROW	Select Row	26548
SelectScenario	AMT	SID_SELECT_SCENARIO	Select Scenario	26378
SelectTables	AMT	SID_SELECT_TABLES	Select	26090
SetInputMode	AMT	SID_SETINPUTMODE	Set Input Mode	26552
SetOptimalColumnWidth	AMT	FID_COL_OPT_WIDTH	Optimal Width	26286
SetOptimalColumnWidthDirect	AMT	FID_COL_OPT_DIRECT	Optimal Column Width, direct	26299
SetOptimalRowHeight	AMT	FID_ROW_OPT_HEIGHT	Optimal Height	26282
SheetRightToLeft	AMT	FID_TAB_RTL	Right-To-Left	26352

Show	AMT	FID_TABLE_SHOW	Show	26290
ShowChanges	AMT	FID_CHG_SHOW	Show	26239
ShowColumn	AMT	FID_COL_SHOW	Show	26288
ShowDependents	AMT	SID_DETECTIVE_ADD_SUCC	Trace Dependents	26458
ShowErrors	AMT	SID_DETECTIVE_ADD_ERR	Trace Error	26460
ShowInvalid	AMT	SID_DETECTIVE_INVALID	Mark Invalid Data	26469
ShowPrecedents	AMT	SID_DETECTIVE_ADD_PRED	Trace Precedents	26456
ShowRow	AMT	FID_ROW_SHOW	Show	26284
SimpleReferenz	AMT	WID_SIMPLE_REF	Enter References	25728
SortAscending	AMT	SID_SORT_ASCENDING	Sort Ascending	26344
SortDescending	AMT	SID_SORT_DESCENDING	Sort Descending	26343
SplitCell	AMT	FID_MERGE_OFF	Split Cells	26294
SplitWindow	AMT	SID_WINDOW_SPLIT	Split	26069
StandardTextAttributes	AMT	SID_TEXT_STANDARD	Standard Text Attributes	26296
StarChartDataDialog	AMT	SID_OPENDLG_MODCHART	Modify Chart Data Area	26158
StarChartDialog	AMT	SID_OPENDLG_CHART	Chart	26155
StatusDocPos	S	SID_STATUS_DOCPOS	Position in Document	26114
StatusPageStyle	S	SID_STATUS_PAGESTYLE	Page Format	26115
StatusSelectionMode	S	SID_STATUS_SELMODE	Selection Mode	26116
StatusSelectionModeExp	AMT	SID_STATUS_SELMODE_ERG	Status Expanded Selection	26122
StatusSelectionModeExt	AMT	SID_STATUS_SELMODE_ERW	Status Extended Selection	26123
TableOperationDialog	AMT	SID_OPENDLG_TABOP	Multiple Operations	26154
TableSelectAll	AMT	FID_TAB_SELECTALL	Select All Sheets	26349
TextAttributes	AMT	SID_DRAWTEXT_ATTR_DLG	NO DESCRIPTION AVAILABLE	26297
ToggleAnchorType	AMT	SID_ANCHOR_TOGGLE	Change Anchor	26412
ToggleMergeCells	AMT	FID_MERGE_TOGGLE	Merge Cells	26581
ToggleRelative	AMT	SID_TOGGLE_REL	Relative/Absolute References	26609
ToolProtectionDocument	AMT	FID_PROTECT_DOC	Document	26307
ToolsOptions	AMT	SID_SCOPTIONS	Spreadsheet Options	26309
TraceChangeMode	AMT	FID_CHG_RECORD	Record	26238
UnderlineDotted	AMT	SID_ULINE_VAL_DOTTED	Underline: Dotted	26649
UnderlineDouble	AMT	SID_ULINE_VAL_DOUBLE	Underline: Double	26648

UnderlineNone	AMT	SID_ULINE_VAL_NONE	Underline: Off	26646
UnderlineSingle	AMT	SID_ULINE_VAL_SINGLE	Underline: Single	26647
UpdateChart	AMT	SID_UPDATECHART	Redraw Chart	26013
Validation	AMT	FID_VALIDATION	Validity	26625
ViewRowColumnHeaders	AMT	FID_TOGGLEHEADERS	Column & Row Headers	26242
ViewValueHighlighting	AMT	FID_TOGGLESYNTAX	Value Highlighting	26245
WrapText	AMT	SID_ATTR_ALIGN_LINEBREAK	Automatic Row Break	10230
ZoomIn	AMT	SID_PREVIEW_ZOOMIN	NO DESCRIPTION AVAILABLE	26501
ZoomOut	AMT	SID_PREVIEW_ZOOMOUT	Zoom Out	26502

## Draw/Impress commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
ActionMode	AMT	SID_ACTIONMODE	Allow Interaction	27060
AdvancedMode	AMT	SID_OBJECT_CHOOSE_MODE	Effects	27095
AnimationEffects	AMT	SID_ANIMATION_EFFECTS	Interaction	27063
AnimationObjects	AMT	SID_ANIMATION_OBJECTS	Animated Image	27062
ArrowsToolbox	AMT	SID_DRAWTBX_ARROWS	Lines and Arrows	27171
AssignLayout	AMT	SID_ASSIGN_LAYOUT	NO DESCRIPTION AVAILABLE	27435
Backward	AMT	SID_MOREBACK	Send Backward	27032
BeforeObject	AMT	SID_BEFORE_OBJ	In Front of Object	27326
BehindObject	AMT	SID_BEHIND_OBJ	Behind Object	27116
BigHandles	AMT	SID_BIG_HANDLES	Large Handles	27168
Break	AMT	SID_BREAK	Break	27094
Bullet	AMT	SID_BULLET	Special Character	27019
CapturePoint	AMT	SID_CAPTUREPOINT	Insert Snap Point/Line	27038
ChangeBezier	AMT	SID_CHANGEBEZIER	To Curve	27036
ChangePolygon	AMT	SID_CHANGEPOLYGON	To Polygon	27037
ClickChangeRotation	AMT	SID_CLICK_CHANGE_ROTATION	Rotation Mode after Clicking Object	27170
CloseMasterView	AMT	SID_CLOSE_MASTER_VIEW	Close Master View	27434

ColorView	AMT	SID_COLORVIEW	Black & White View	27257
Combine	AMT	SID_COMBINE	Combine	27026
Cone	AMT	SID_3D_CONE	Cone	27299
Connect	AMT	SID_CONNECT	Connect	27093
Connector	AMT	SID_TOOL_CONNECTOR	Connector	27058
ConnectorArrowEnd	AMT	SID_CONNECTOR_ARROW_END	Connector Ends with Arrow	27120
ConnectorArrowStart	AMT	SID_CONNECTOR_ARROW_START	Connector Starts with Arrow	27119
ConnectorArrows	AMT	SID_CONNECTOR_ARROWS	Connector with Arrows	27121
ConnectorAttributes	AMT	SID_CONNECTION_DLG	Connector	27338
ConnectorCircleEnd	AMT	SID_CONNECTOR_CIRCLE_END	Connector Ends with Circle	27123
ConnectorCircleStart	AMT	SID_CONNECTOR_CIRCLE_START	Connector Starts with Circle	27122
ConnectorCircles	AMT	SID_CONNECTOR_CIRCLES	Connector with Circles	27124
ConnectorCurve	AMT	SID_CONNECTOR_CURVE	Curved Connector	27132
ConnectorCurveArrowEnd	AMT	SID_CONNECTOR_CURVE_ARROW_END	Curved Connector Ends with Arrow	27134
ConnectorCurveArrowStart	AMT	SID_CONNECTOR_CURVE_ARROW_START	Curved Connector Starts with Arrow	27133
ConnectorCurveArrows	AMT	SID_CONNECTOR_CURVE_ARROWS	Curved Connector with Arrows	27135
ConnectorCurveCircleEnd	AMT	SID_CONNECTOR_CURVE_CIRCLE_END	Curved Connector Ends with Circle	27137
ConnectorCurveCircleStart	AMT	SID_CONNECTOR_CURVE_CIRCLE_START	Curved Connector Starts with Circle	27136
ConnectorCurveCircles	AMT	SID_CONNECTOR_CURVE_CIRCLES	Curved Connector with Circles	27138
ConnectorLine	AMT	SID_CONNECTOR_LINE	Straight Connector	27125
ConnectorLineArrowEnd	AMT	SID_CONNECTOR_LINE_ARROW_END	Straight Connector ends with Arrow	27127
ConnectorLineArrowStart	AMT	SID_CONNECTOR_LINE_ARROW_START	Straight Connector starts with Arrow	27126
ConnectorLineArrows	AMT	SID_CONNECTOR_LINE_ARROWS	Straight Connector with Arrows	27128
ConnectorLineCircleEnd	AMT	SID_CONNECTOR_LINE_CIRCLE_END	Straight Connector ends with Circle	27130
ConnectorLineCircleStart	AMT	SID_CONNECTOR_LINE_CIRCLE_START	Straight Connector starts with Circle	27129
ConnectorLineCircles	AMT	SID_CONNECTOR_LINE_CIRCLES	Straight Connector with Circles	27131
ConnectorLines	AMT	SID_CONNECTOR_LINES	Line Connector	27139
ConnectorLinesArrowEnd	AMT	SID_CONNECTOR_LINES_ARROW_END	Line Connector Ends with Arrow	27141
ConnectorLinesArrowStart	AMT	SID_CONNECTOR_LINES_ARROW_START	Line Connector Starts with Arrow	27140
ConnectorLinesArrows	AMT	SID_CONNECTOR_LINES_ARROWS	Line Connector with Arrows	27142
ConnectorLinesCircleEnd	AMT	SID_CONNECTOR_LINES_CIRCLE_END	Line Connector Ends with Circle	27144
ConnectorLinesCircleStart	AMT	SID_CONNECTOR_LINES_CIRCLE_START	Line Connector Starts with Circle	27143

ConnectorLinesCircles	AMT	SID_CONNECTOR_LINES_CIRCLES	Line Connector with Circles	27145
ConnectorToolbox	AMT	SID_DRAWTBX_CONNECTORS	Connector	27028
ConvertInto3D	AMT	SID_CONVERT_TO_3D	To 3D	10648
ConvertInto3DLathe	AMT	SID_CONVERT_TO_3D_LATHE	In 3D Rotation Object	27008
ConvertInto3DLatheFast	AMT	SID_CONVERT_TO_3D_LATHE_FAST	To 3D Rotation Object	10649
ConvertIntoBitmap	AMT	SID_CONVERT_TO_BITMAP	To Bitmap	27378
ConvertIntoMetaFile	AMT	SID_CONVERT_TO_METAFILE	To Metafile	27379
ConvertTo1BitMatrix	AMT	SID_CONVERT_TO_1BIT_MATRIX	1 Bit Dithered	27162
ConvertTo1BitThreshold	AMT	SID_CONVERT_TO_1BIT_THRESHOLD	1 Bit Threshold	27161
ConvertTo4BitColors	AMT	SID_CONVERT_TO_4BIT_COLORS	4 Bit color palette	27164
ConvertTo4BitGrays	AMT	SID_CONVERT_TO_4BIT_GRAYS	4 Bit grayscales	27163
ConvertTo8BitColors	AMT	SID_CONVERT_TO_8BIT_COLORS	8 Bit color palette	27166
ConvertTo8BitGrays	AMT	SID_CONVERT_TO_8BIT_GRAYS	8 Bit Grayscales	27165
ConvertToTrueColor	AMT	SID_CONVERT_TO_24BIT	24 Bit True Color	27167
CopyObjects	AMT	SID_COPYOBJECTS	Duplicate	27004
CrookRotate	AMT	SID_OBJECT_CROOK_ROTATE	Set in Circle (perspective)	27090
CrookSlant	AMT	SID_OBJECT_CROOK_SLANT	Set to circle (slant)	27091
CrookStretch	AMT	SID_OBJECT_CROOK_STRETCH	Set in Circle (distort)	27092
Cube	AMT	SID_3D_CUBE	Cube	27296
CustomAnimation	AMT	SID_CUSTOM_ANIMATION_PANEL	Custom Animation	27328
CustomAnimationSchemes	AMT	SID_CUSTOM_ANIMATION_SCHEMES_PANEL	Animation Schemes	27333
CustomShowDialog	AMT	SID_CUSTOMSHOW_DLG	Custom Slide Show	27365
Cylinder	AMT	SID_3D_CYLINDER	Cylinder	27298
Cyramid	AMT	SID_3D_PYRAMID	Pyramid	27300
DeleteLayer	AMT	SID_DELETE_LAYER	Delete	27081
DeleteMasterPage	AMT	SID_DELETE_MASTER_PAGE	Delete Master	27432
DeletePage	AMT	SID_DELETE_PAGE	Delete Slide	27080
DiaMode	AMT	SID_DIAMODE	Slide Sorter	27011
Dismantle	AMT	SID_DISMANTLE	Split	27082
DisplayMasterBackground	AMT	SID_DISPLAY_MASTER_BACKGROUND	NO DESCRIPTION AVAILABLE	27436
DisplayMasterObjects	AMT	SID_DISPLAY_MASTER_OBJECTS	NO DESCRIPTION AVAILABLE	27437
DoubleClickTextEdit	AMT	SID_DOUBLECLICK_TEXTEDIT	Double-click to edit Text	27169

DrawingMode	AMT	SID_DRAWINGMODE	Drawing View	27009
DuplicatePage	AMT	SID_DUPLICATE_PAGE	Duplicate Slide	27342
EditHyperlink	AMT	SID_EDIT_HYPERLINK	Hyperlink	27382
EllipseToolbox	AMT	SID_DRAWTBX_ELLIPSES	Ellipse	10400
ExpandPage	AMT	SID_EXPAND_PAGE	Expand Slide	27343
FillDraft	AMT	SID_FILL_DRAFT	Contour Mode	27147
Forward	AMT	SID_MOREFRONT	Bring Forward	27031
GlueEditMode	AMT	SID_GLUE_EDITMODE	Glue Points	27301
GlueEscapeDirection	AMT	SID_GLUE_ESCDIR	Exit Direction	27304
GlueEscapeDirectionBottom	AMT	SID_GLUE_ESCDIR_BOTTOM	Exit Direction Bottom	27317
GlueEscapeDirectionLeft	AMT	SID_GLUE_ESCDIR_LEFT	Exit Direction Left	27314
GlueEscapeDirectionRight	AMT	SID_GLUE_ESCDIR_RIGHT	Exit Direction Right	27315
GlueEscapeDirectionTop	AMT	SID_GLUE_ESCDIR_TOP	Exit Direction Top	27316
GlueHorzAlignCenter	AMT	SID_GLUE_HORZALIGN_CENTER	Glue Point Horizontal Center	27305
GlueHorzAlignLeft	AMT	SID_GLUE_HORZALIGN_LEFT	Glue Point Horizontal Left	27306
GlueHorzAlignRight	AMT	SID_GLUE_HORZALIGN_RIGHT	Glue Point Horizontal Right	27307
GlueInsertPoint	AMT	SID_GLUE_INSERT_POINT	Insert Glue Point	27302
GluePercent	AMT	SID_GLUE_PERCENT	Glue Point Relative	27303
GlueVertAlignBottom	AMT	SID_GLUE_VERTALIGN_BOTTOM	Glue Point Vertical Bottom	27310
GlueVertAlignCenter	AMT	SID_GLUE_VERTALIGN_CENTER	Glue Point Vertical Center	27308
GlueVertAlignTop	AMT	SID_GLUE_VERTALIGN_TOP	Glue Point Vertical Top	27309
GraphicDraft	AMT	SID_GRAPHIC_DRAFT	Picture Placeholders	27146
GridFront	AMT	SID_GRID_FRONT	Grid to Front	27323
HalfSphere	AMT	SID_3D_HALF_SPHERE	Half-Sphere	27313
HandlesDraft	AMT	SID_HANDLES_DRAFT	Simple Handles	27150
HandoutMasterPage	AMT	SID_HANDOUT_MASTERPAGE	Handout Master	27349
HandoutMode	AMT	SID_HANDOUTMODE	Handout Page	27070
HeaderAndFooter	AMT	SID_HEADER_AND_FOOTER	Header and Footer	27407
HelplinesFront	AMT	SID_HELPLINES_FRONT	Guides to Front	27325
HelplinesUse	AMT	SID_HELPLINES_USE	Snap to Guides	27152
HelplinesVisible	AMT	SID_HELPLINES_VISIBLE	Display Guides	27324
HideSlide	AMT	SID_HIDE_SLIDE	Show/Hide Slide	10161

Hyphenation	AMT	SID_HYPHENATION	Hyphenation	27340
ImportFromFile	AMT	SID_INSERTFILE	File	27015
InsertAuthorField	AMT	SID_INSERT_FLD_AUTHOR	Author	27364
InsertDateAndTime	AMT	SID_INSERT_DATE_TIME	Date and Time	27412
InsertDateFieldFix	AMT	SID_INSERT_FLD_DATE_FIX	Date (fixed)	27358
InsertDateFieldVar	AMT	SID_INSERT_FLD_DATE_VAR	Date (variable)	27357
InsertFileField	AMT	SID_INSERT_FLD_FILE	File Name	27363
InsertLayer	AMT	SID_INSERTLAYER	Layer	27043
InsertMasterPage	AMT	SID_INSERT_MASTER_PAGE	New Master	27431
InsertPage	AMT	SID_INSERTPAGE	Slide	27014
InsertPageField	AMT	SID_INSERT_FLD_PAGE	Page Number	27361
InsertPageNumber	AMT	SID_INSERT_PAGE_NUMBER	Page Number	27411
InsertPageQuick	AMT	SID_INSERTPAGE_QUICK	Insert Slide Direct	27352
InsertTimeFieldFix	AMT	SID_INSERT_FLD_TIME_FIX	Time (fixed)	27360
InsertTimeFieldVar	AMT	SID_INSERT_FLD_TIME_VAR	Time (variable)	27359
InsertToolbox	AMT	SID_DRAWTBX_INSERT	Insert	27318
InteractiveGradient	AMT	SID_OBJECT_GRADIENT	Gradient	27101
InteractiveTransparence	AMT	SID_OBJECT_TRANSPARENCE	Transparency	27100
LayerMode	AMT	SID_LAYERMODE	Layer	27050
LayoutStatus	S	SID_STATUS_LAYOUT	Layout	27087
LeaveAllGroups	AMT	SID_LEAVE_ALL_GROUPS	Exit All Groups	27345
LineArrowCircle	AMT	SID_LINE_ARROW_CIRCLE	Line with Arrow/Circle	27175
LineArrowEnd	AMT	SID_LINE_ARROW_END	Line Ends with Arrow	27173
LineArrowSquare	AMT	SID_LINE_ARROW_SQUARE	Line with Arrow/Square	27177
LineArrowStart	AMT	SID_LINE_ARROW_START	Line Starts with Arrow	27172
LineArrows	AMT	SID_LINE_ARROWS	Line with Arrows	27174
LineCircleArrow	AMT	SID_LINE_CIRCLE_ARROW	Line with Circle/Arrow	27176
LineDraft	AMT	SID_LINE_DRAFT	Line Contour Only	27149
LineSquareArrow	AMT	SID_LINE_SQUARE_ARROW	Line with Square/Arrow	27178
LineToolbox	AMT	SID_DRAWTBX_LINES	Curve	10401
ManageLinks	AMT	SID_MANAGE_LINKS	Links	27005
MasterLayouts	AMT	SID_MASTER_LAYOUTS	Master Elements	27408



MasterPage	AMT	SID_MASTERPAGE	Master	27053
MeasureAttributes	AMT	SID_MEASURE_DLГ	Dimensions	27320
MeasureLine	AMT	SID_DRAW_MEASURELINE	Dimension Line	27051
Mirror	AMT	SID_OBJECT_MIRROR	Flip	27085
MirrorHorz	AMT	SID_HORIZONTAL	Horizontally	27035
MirrorVert	AMT	SID_VERTICAL	Vertically	27034
ModifyField	AMT	SID_MODIFY_FIELD	Fields	27362
ModifyLayer	AMT	SID_MODIFYLAYER	Layer	27048
ModifyPage	AMT	SID_MODIFYPAGE	Slide Layout	27046
Morphing	AMT	SID_POLYGON_MORPHING	Cross-fading	27319
NameGroup	AMT	SID_NAME_GROUP	Name Object	27027
NewRouting	AMT	SID_CONNECTION_NEW_ROUTING	Reset Routing	27341
NotesMasterPage	AMT	SID_NOTES_MASTERPAGE	Notes Master	27350
NotesMode	AMT	SID_NOTESMODE	Notes Page	27069
ObjectPosition	AMT	SID_POSITION	Arrange	27022
Objects3DToolbox	AMT	SID_DRAWTBX_3D_OBJECTS	3D Objects	27295
OutlineMode	AMT	SID_OUTLINEMODE	Outline	27010
OutputQualityBlackWhite	AMT	SID_OUTPUT_QUALITY_BLACKWHITE	Black and White	27368
OutputQualityColor	AMT	SID_OUTPUT_QUALITY_COLOR	Color	27366
OutputQualityContrast	AMT	SID_OUTPUT_QUALITY_CONTRAST	High Contrast	27400
OutputQualityGrayscale	AMT	SID_OUTPUT_QUALITY_GRAYSCALE	Grayscale	27367
PackAndGo	AMT	SID_PACKNGO	Pack	27380
PageMode	AMT	SID_PAGEMODE	Normal	27049
PageSetup	AMT	SID_PAGESETUP	Page	27002
PageStatus	S	SID_STATUS_PAGE	Slide/Layer	27086
PagesPerRow	AMT	SID_PAGES_PER_ROW	Slides Per Row	27284
ParaspaceDecrease	AMT	SID_PARASPACE_DECREASE	Decrease Spacing	27347
ParaspaceIncrease	AMT	SID_PARASPACE_INCREASE	Increase Spacing	27346
PasteClipboard	AMT	SID_PASTE2	Paste Special	27003
PickThrough	AMT	SID_PICK_THROUGH	Select Text Area Only	27159
PixelMode	AMT	SID_PIXELMODE	Pixel Mode	27021
Polygon	AMT	SID_DRAW_POLYGON	Polygon, filled	10117

Presentation	AMT	SID_PRESENTATION	Slide Show	10157
PresentationDialog	AMT	SID_PRESENTATION_DLG	Slide Show Settings	27339
PresentationLayout	AMT	SID_PRESENTATION_LAYOUT	Slide Design	27064
PreviewWindow	AMT	SID_PREVIEW_WIN	Preview	27327
QuickEdit	AMT	SID_QUICKEDIT	Allow Quick Editing	27158
RectangleToolbox	AMT	SID_DRAWTBX_RECTANGLES	Rectangle	10399
RehearseTimings	AMT	SID_REHEARSE_TIMINGS	Rehearse Timings	10159
RenameLayer	AMT	SID_RENAMELAYER	Rename	27269
RenameMasterPage	AMT	SID_RENAME_MASTER_PAGE	Rename Master	27433
RenamePage	AMT	SID_RENAMEPAGE	Rename Slide	27268
ReverseOrder	AMT	SID_REVERSE_ORDER	Reverse	27117
Shear	AMT	SID_OBJECT_SHEAR	Distort	27107
Shell3D	AMT	SID_3D_SHELL	Shell	27311
SlideChangeWindow	AMT	SID_SLIDE_TRANSITIONS_PANEL	Slide Transition	27334
SlideMasterPage	AMT	SID_SLIDE_MASTERPAGE	Slide Master	27348
SnapBorder	AMT	SID_SNAP_BORDER	Snap to Page Margins	27155
SnapFrame	AMT	SID_SNAP_FRAME	Snap to Object Border	27156
SnapPoints	AMT	SID_SNAP_POINTS	Snap to Object Points	27157
SolidCreate	AMT	SID_SOLID_CREATE	Create Object with Attributes	27151
Sphere	AMT	SID_3D_SPHERE	Sphere	27297
SummaryPage	AMT	SID_SUMMARY_PAGE	Summary Slide	27344
TextAttributes	AMT	SID_TEXTATTR_DLG	Text	27281
TextDraft	AMT	SID_TEXT_DRAFT	Text Placeholders	27148
TextFitToSizeTool	AMT	SID_TEXT_FITTO_SIZE	Fit Text to Frame	27285
TextToolbox	AMT	SID_DRAWTBX_TEXT	Text	10398
TitleMasterPage	AMT	SID_TITLE_MASTERPAGE	Title Slide Master	27351
Torus	AMT	SID_3D_TORUS	Torus	27312
VerticalTextFitToSizeTool	AMT	SID_TEXT_FITTO_SIZE_VERTICAL	Fit Vertical Text to Frame	27286
ZoomPanning	AMT	SID_ZOOM_PANNING	Shift	27017
convert_to_contour	AMT	SID_CONVERT_TO_CONTOUR	To Contour	27381

## Chart commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
AllTitles	AMT	SID_DIAGRAM_TITLE_ALL	All Titles	30562
Backward	AMT	SID_ROW_MOREBACK	NO DESCRIPTION AVAILABLE	30595
BarWidth	AMT	SID_DIAGRAM_BARWIDTH	Bar Width	30591
ChartTitle	AMT	SID_CHART_TITLE	Chart Title	30520
ContextType	AMT	SID_CONTEXT_TYPE	Chart Type	30538
DataDescriptionType	AMT	SID_DIAGRAM_DATADESCRIPTION	Caption Type for Chart Data	30588
DataInColumns	AMT	SID_DATA_IN_COLUMNS	Data in Columns	30536
DataInRows	AMT	SID_DATA_IN_ROWS	Data in Rows	30535
DefaultColors	AMT	SID_DIAGRAM_DEFAULTCOLORS	Default Colors for Data Series	30590
DiagramArea	AMT	SID_DIAGRAM_AREA	Chart Area	30526
DiagramAxisA	AMT	SID_DIAGRAM_AXIS_A	Secondary X Axis	30616
DiagramAxisAll	AMT	SID_DIAGRAM_AXIS_ALL	All Axes	30555
DiagramAxisB	AMT	SID_DIAGRAM_AXIS_B	Secondary Y Axis	30617
DiagramAxisX	AMT	SID_DIAGRAM_AXIS_X	X Axis	30552
DiagramAxisY	AMT	SID_DIAGRAM_AXIS_Y	Y Axis	30553
DiagramAxisZ	AMT	SID_DIAGRAM_AXIS_Z	Z Axis	30554
DiagramData	AMT	SID_DIAGRAM_DATA	Chart Data	30514
DiagramFloor	AMT	SID_DIAGRAM_FLOOR	Chart Floor	30525
DiagramGrid	AMT	SID_DIAGRAM_GRID	Edit Grid	30523
DiagramGridAll	AMT	SID_DIAGRAM_GRID_ALL	All Axis Grids	30566
DiagramGridXHelp	AMT	SID_DIAGRAM_GRID_X_HELP	Y Axis Minor Grid	30578
DiagramGridXMain	AMT	SID_DIAGRAM_GRID_X_MAIN	Y Axis Main Grid	30563
DiagramGridYHelp	AMT	SID_DIAGRAM_GRID_Y_HELP	X Axis Minor Grid	30579
DiagramGridYMain	AMT	SID_DIAGRAM_GRID_Y_MAIN	X Axis Main Grid	30564
DiagramGridZHelp	AMT	SID_DIAGRAM_GRID_Z_HELP	Z Axis Minor Grid	30580
DiagramGridZMain	AMT	SID_DIAGRAM_GRID_Z_MAIN	Z Axis Main Grid	30565
DiagramObjects	AMT	SID_DIAGRAM_OBJECTS	Object Properties	30572
DiagramType	AMT	SID_DIAGRAM_TYPE	Chart Type	30528

DiagramWall	AMT	SID_DIAGRAM_WALL	Chart Wall	30524
Forward	AMT	SID_ROW_MOREFRONT	NO DESCRIPTION AVAILABLE	30594
InsertAxis	AMT	SID_INSERT_AXIS	Axes	30518
InsertDescription	AMT	SID_INSERT_DESCRIPTION	Data Labels	30517
InsertGrids	AMT	SID_INSERT_GRIDS	Grids	30540
InsertLegend	AMT	SID_INSERT_CHART_LEGEND	Legend	30516
InsertStatistics	AMT	SID_INSERT_STATISTICS	Statistics	30556
InsertTitle	AMT	SID_INSERT_TITLE	Title	30515
Legend	AMT	SID_LEGEND	Legend	30521
LegendPosition	AMT	SID_DIAGRAM_POSLEGEND	Legend Position	30589
MainTitle	AMT	SID_DIAGRAM_TITLE_MAIN	Main Title	30557
NewArrangement	AMT	SID_NEW_ARRANGEMENT	Reorganize Chart	30539
NumberOfLines	AMT	SID_DIAGRAM_NUMLINES	Number of lines in combination chart	30592
ScaleText	AMT	SID_SCALE_TEXT	Scale Text	30586
SubTitle	AMT	SID_DIAGRAM_TITLE_SUB	Subtitle	30558
ToggleAxisDescr	AMT	SID_TOGGLE_AXIS_DESCR	Show/Hide Axis Description(s)	30532
ToggleAxisTitle	AMT	SID_TOGGLE_AXIS_TITLE	AxesTitle On/Off	30531
ToggleGridHorizontal	AMT	SID_TOGGLE_GRID_HORZ	Horizontal Grid On/Off	30533
ToggleGridVertical	AMT	SID_TOGGLE_GRID_VERT	Vertical Grid On/Off	30534
ToggleLegend	AMT	SID_TOGGLE_LEGEND	Legend On/Off	30530
ToggleTitle	AMT	SID_TOGGLE_TITLE	Title On/Off	30529
ToolSelect	AMT	SID_TOOL_SELECT	Select Tool	30537
Update	AMT	SID_UPDATE	Update Chart	30546
View3D	AMT	SID_3D_VIEW	3D View	30527
XTitle	AMT	SID_DIAGRAM_TITLE_X	Title (X Axis)	30559
YTitle	AMT	SID_DIAGRAM_TITLE_Y	Title (Y Axis)	30560
ZTitle	AMT	SID_DIAGRAM_TITLE_Z	Title (Z Axis)	30561

## Math commands

Commands	GUI Elements	Internal definitions of commands ID	Short Description	ID
Adjust	AMT	SID_ADJUST	Show All	30269
ChangeAlignment	AMT	SID_ALIGN	Alignment	30309
ChangeDistance	AMT	SID_DISTANCE	Spacing	30308
ChangeFont	AMT	SID_FONT	Fonts	30306
ChangeFontSize	AMT	SID_FONTSIZE	Font Size	30307
Draw	AMT	SID_DRAW	Update	30268
FitInWindow	AMT	SID_FITINWINDOW	Fit To Window	30359
FormelCursor	AMT	SID_FORMULACURSOR	Formula Cursor	30271
InsertCommand	AMT	SID_INSERTCOMMAND	Insert Command	30361
InsertConfigName	AMT	SID_INSERTTEXT	Insert Text	30360
InsertFormula	AMT	SID_INSERT_FORMULA	NO DESCRIPTION AVAILABLE	30314
ModifyStatus	S	SID_MODIFYSTATUS	Modified	30366
NextError	AMT	SID_NEXterr	Next Error	30257
NextMark	AMT	SID_NEXTMARK	Next Marker	30259
Preferences	AMT	SID_PREFERENCES	Options	30262
PrevError	AMT	SID_PREVERR	Previous Error	30258
PrevMark	AMT	SID_PREVMARK	Previous Marker	30260
RedrawAutomatic	AMT	SID_AUTO_REDRAW	AutoUpdate Display	30311
SymbolCatalogue	AMT	SID_SYMBOLS_CATALOGUE	Catalog	30261
Symbols	AMT	SID_SYMBOLS	Symbols	30312
TextStatus	S	SID_TEXTSTATUS	Text Status	30367
Textmode	AMT	SID_TEXTMODE	Text Mode	30313
ToolBox	AMT	SID_TOOLBOX	Selection	30270
View100	AMT	SID_VIEW100	1	30264
View200	AMT	SID_VIEW200	2	30265
View50	AMT	SID_VIEW050	0.5	30263
ZoomIn	AMT	SID_ZOOMIN	NO DESCRIPTION AVAILABLE	30266
ZoomOut	AMT	SID_ZOOMOUT	NO DESCRIPTION AVAILABLE	30267

